

Plug-in Reference

 **WAVELAB PRO 11**  
Audio Editing And Mastering Suite

The Steinberg Documentation Team: Cristina Bachmann, Heiko Bischoff, Lillie Harris, Christina Kaboth, Insa Mingers, Matthias Obrecht, Sabine Pfeifer, Benjamin Schütte

Translation: Ability InterBusiness Solutions (AIBS), Moon Chen, Jérémie Dal Santo, Rosa Freitag, Josep Llodra Grimalt, Vadim Kupriianov, Filippo Manfredi, Roland Münchow, Boris Rogowski, Sergey Tamarovsky

This document provides improved access for people who are blind or have low vision. Please note that due to the complexity and number of images in this document, it is not possible to include text descriptions of images.

The information in this document is subject to change without notice and does not represent a commitment on the part of Steinberg Media Technologies GmbH. The software described by this document is subject to a License Agreement and may not be copied to other media except as specifically allowed in the License Agreement.

No part of this publication may be copied, reproduced, or otherwise transmitted or recorded, for any purpose, without prior written permission by Steinberg Media Technologies GmbH. Registered licensees of the product described herein may print one copy of this document for their personal use.

All product and company names are ™ or ® trademarks of their respective owners. For more information, please visit [www.steinberg.net/trademarks](http://www.steinberg.net/trademarks).

© Steinberg Media Technologies GmbH, 2022.

All rights reserved.

WaveLab Pro\_11.0.20\_en-US\_2021-12-01

# Table of Contents

<b>4</b>	<b>WaveLab-specific Plug-ins</b>	<b>122</b>	<b>Legacy Plug-ins</b>
4	Resampler	<b>123</b>	<b>Dithering Plug-ins</b>
4	Leveler	123	Internal Dithering
5	Leveler Multi	123	Lin Pro Dither
5	MasterRig	<b>125</b>	<b>Batch Processing Plug-ins</b>
22	Peak Master	125	Audio Analyzer
23	RestoreRig	127	Audio Injector
28	Silence	127	Audio Mixer
28	Stereo Expander	128	DC Remover
<b>29</b>	<b>Steinberg VST 3 Plug-ins</b>	128	Delay Next Process Activation
29	AutoPan	128	Fade In/Fade Out
30	Brickwall Limiter	129	Instructor
31	Channel Extractor	130	Level Normalizer
31	Chorus	130	Loudness Meta Normalizer
32	Compressor	131	Loudness Restorer
33	CurveEQ	132	Meta Leveler
34	DeEsser	132	Resizer
36	DeReverb	132	Stereo to Mono
37	Distortion	133	Trimmer
38	DualFilter	<b>134</b>	<b>Index</b>
38	EnvelopeShaper		
39	Expander		
40	Frequency 2		
47	Gate		
48	GEQ-10/GEQ-30		
50	Imager		
52	Limiter		
52	L/R to M/S, M/S to L/R		
53	Magneto II		
54	Maximizer		
55	Mix6to2		
56	Mix8to2		
57	MonoDelay		
57	MonoToStereo		
58	MultibandCompressor		
61	MultibandEnvelopeShaper		
63	MultibandExpander		
65	Octaver		
65	PingPongDelay		
67	PostFilter		
69	Quadrafuzz v2		
72	REvelation		
74	RoomWorks		
77	RoomWorks SE		
78	Squasher		
81	SuperVision		
109	StereoDelay		
110	StereoEnhancer		
111	Stereo Tools		
112	StudioChorus		
113	StudioEQ		
115	TestGenerator		
116	Tube Compressor		
117	VintageCompressor		
118	VSTDynamics		

# WaveLab-specific Plug-ins

WaveLab-specific plug-ins use the plug-in format of WaveLab, and cannot be used with other applications.


- WaveLab-specific plug-ins can only be used in the **Master Section** and in batch processes. However, some WaveLab effects are also included as VST plug-ins, available as track or clip effects in audio montages.
- You can specify which plug-ins should be available on the **Effects** pane and the **Final Effects/Dithering** pane of the **Master Section** by using the **Plug-in Settings** dialog.
- When a multichannel configuration is used in the audio montage, only certain plug-ins can be used as master effects. All channels in the **Master Section** are affected equally.

## Resampler

This plug-in is a professional sample rate converter providing exceptional transparency and preservation of the frequency content. It is only available in the **Master Section**.

### NOTE

This plug-in is very CPU consuming, especially in high quality modes.



### Output Sample Rate


Defines the output sample rate while the input sample rate is determined by the sample rate of the active audio file or audio montage.

### Quality

Defines the quality of the algorithm that is used (**Standard, High, Very High, Best**). In **Standard** mode, the CPU load is much lower than in **Best** mode but the sound quality of the resulting audio is also lower.

## Leveler

This plug-in is useful for correcting an imbalance or adjusting levels between stereo channels, or for mixing down to mono.



### Volume Left/Volume Right (-48 dB to 12 dB)

Governs how much of the signal is included in the left and/or right channel of the output bus.

### Stereo Link

If this option is activated, **Volume Right** delivers the gain that is set for **Volume Left**.

### Mix to Mono

If this option is activated, a mono mix of the stereo channels is delivered to the output bus.

## Leveler Multi

This plug-in takes multichannel input and applies a fader equally to all channels.



### Volume (-48 dB to 12 dB)

Governs how much gain is applied to the signal before it is routed to the output bus.

## MasterRig

**MasterRig** allows you to master audio material in an intuitive and creative way. It offers high-class sound quality, accuracy, flexibility, and control.

## Main Layout

### Module Chain

The module chain contains the mastering modules. You can add up to 8 modules.



The following settings are available for each module:

#### Bypass

Bypasses the module. This allows you to compare the sound of the unprocessed signal to that of the processed signal.

#### Solo


Solos the module. Only one module can be soloed at a time.

#### Remove

Removes the module from the module chain.

### Scenes

You can save up to 4 **MasterRig** configurations as scenes. This allows you to compare different parameter settings and module combinations.



- To copy the settings of a scene to another scene, click **Copy Scene**, and then click the scene button of the scene where you want to paste the settings.  
A copy of a scene is indicated by a **(c)** behind the scene name.


- To reset the settings of the selected scene, click **Reset Scene**.



- To rename a scene, double-click the scene name and type in another name.


## Spectrum Display

The spectrum display in the upper half of the panel is where you set the width of the frequency bands. The vertical value scale to the left shows the gain level of each frequency band. The horizontal scale shows the frequency range.



- To define the frequency range of the different frequency bands, use the handles at the sides of each frequency band.
- To attenuate or boost the output level of each frequency band by  $\pm 15$  dB, use the handles on top of each frequency band.

## Settings



### Parameter Linking

Links the parameters of the same type in all bands in a module. This allows you to edit parameter values of all bands in a module simultaneously. Two link modes are available: **Absolute** and **Relative**.

- If **Absolute Mode** is activated and you edit a parameter value in one band, the corresponding parameter values in the other bands are set to the same value.
- If **Relative Mode** is activated and you edit a parameter value in one band, the corresponding parameter values in the other bands keep their relation.

### Auto Listen for Filters

If this option is activated and you edit a parameter of a module, the corresponding filter or band is soloed. This allows you to locate unwanted frequencies in your audio and helps you to focus on a particular band or filter. Once you stop editing the parameter, **Solo** is deactivated.


### Global Settings

Allows you to make global settings for **MasterRig**.

### Undo/Redo

Undoes/Redoes the last operation. The undo/redo history is deleted when you select another scene.

### Input/Output Meter



The input/output meter provides a combined peak level, with peak-hold functionality and RMS meter. Between the meters for input and output is the gain reduction meter for the **Limitter**.

The maximum values for input/output peak level, RMS, and gain reduction are displayed above the meter display. To reset all maximum values, click any of the values.

### Side-Chain Settings

The **Compressor** module and the **Dynamic EQ** module support side-chain. You can set up the side-chain routing for each band separately.

- To open the side-chain panel, click the **SC** button at the bottom left of each band section.



### Active

Activates the internal side-chain filter. The input signal can then be shaped according to the filter parameters.

### SC FREQ

Sets the frequency of the side-chain filter.

### Auto (Dynamic EQ only)

Deactivates the **SC Frequency** knob of the side-chain panel. Instead, the settings of the **Frequency** knob are used.

### Listen

Allows you to solo the side-chain filter.

### SC Q

Sets the resonance or width of the filter.

## Modules

Modules allow you to create a mastering chain. Some modules can be used only once and some in two instances in the module chain. You can rearrange modules in the module chain to change the processing order.

- To add a module to the module chain, click **Add Module** in the modules section and click a module.
- To remove a module, click the corresponding **Remove** button.
- To bypass a module, click the corresponding **Bypass** button.
- To solo a module, click the corresponding **Solo** button.
- To change the order of the modules, drag a module to another position in the module chain.

## Global Settings

- To open the **Global Settings**, click **Global Settings**  above the spectrum display.

### Spectrum Display

#### Show Spectrum

Activates/Deactivates the spectrum display.

#### Smooth

Determines the reaction time of the spectrum display. Lower values result in faster reaction times.



### Peak Hold

Freezes the peak values of the spectrum display.

### Slope

Tilts the spectrum display around the 1 kHz pivot.

### Two Channels

If this option is activated, the spectrum of the left and right channels are displayed separately.

### EQ Curve

#### Show Curve

Shows/Hides the EQ curve in the spectrum display.

#### Filled

If this option is activated, the EQ curve is filled.

### RMS

#### AES17 (+3 dB)

If this option is activated, the RMS value is raised by 3 dB to follow the AES17 standard.

## Limiter

The **Limiter** module makes sure that the output level never exceeds a set output level, to avoid clipping in following devices.



### Band Settings



### On/Off

Activates/Deactivates the corresponding section.

## Balance



### Mid/Side


Allow you to set the gain for the mid and side signal.

### Solo Mid Signal/Solo Side Signal

Allow you to solo the mid or side signal.

## Transients

If the **Transients** section is activated, you can set the following parameters:



### ATT

Sets the gain of the attack phase of the signal for the corresponding band.

### REL

Sets the gain of the release phase of the signal for the corresponding band.

### Gain

Sets the output level for the corresponding band.

## Harmonics

If the **Harmonics** section is activated, the **Limiter** module starts limiting the signal softly. At the same time, harmonics are generated, adding a warm, tube-like characteristic to the audio material.



### 2nd HARM/3rd HARM

Allow you to control the second and third harmonic independently.

### Drive

Allows you to adjust the amount of gain boost for the signal to raise the amount of soft-clipping.

## Brickwall

Due to its fast attack time, **Brickwall Limiter** can reduce even short audio level peaks without creating audible artifacts. The limiting amount is displayed between the input and the output meter.



### Release

Sets the time after which the gain returns to the original level when the signal drops below the threshold. If **Auto Release** is activated, the plug-in automatically finds the best release setting for the audio material.

### Oversample

If this option is activated, **Brickwall Limiter** detects and limits signal levels between two samples to prevent distortion when converting digital signals into analog signals.

### Stereo Link

If this option is activated, **Brickwall Limiter** uses the channel with the highest level to analyze the input signal. If the button is deactivated, each channel is analyzed separately.

### Output

Sets the output level.

## Maximizer

**Maximizer** raises the loudness of audio material without the risk of clipping. The limiting amount is displayed between the input and the output meter.



### Optimize

Determines the loudness of the signal.

### Output

Sets the output level.

## Compressor

The **Compressor** module allows a signal to be split into four frequency bands. You can specify the level, bandwidth, and compressor characteristics for each band.

You can add two **Compressor** modules to the module chain, **Compressor A** and **Compressor B**.



## Band Settings



### On/Off

Activates/Deactivates the corresponding section.

### Solo Band




Solos the corresponding frequency band.

### Channel Settings

Allow you to switch between left/right, stereo, and mid/side processing. In **Left/Right** or **Mid/Side** processing mode, you can make different settings for the two channels.

### Add/Remove Band

Allow you to add and remove bands.



### Standard

Allows you to create smooth compression effects.



#### THRESH (-60 to 0 dB)

Signal levels above the set threshold trigger the compressor.

#### ATT (0.1 to 100 ms)

Determines how fast the compressor responds. If the attack time is long, more of the initial part of the signal passes through unprocessed.

#### REL (10 to 1000 ms)

Sets the time after which the gain returns to its original level. If **Auto Release** is activated, the plug-in automatically finds a suitable release setting for the audio.

#### Ratio

Sets the amount of gain reduction applied to signal above the set threshold.

#### Mix

Sets the level balance between the dry signal and the wet signal.

#### Compressor curve display

Graphically illustrates the compressor curve that is shaped according to the **Threshold** and **Ratio** parameter settings.

### Output

Sets the output gain.

### Side-Chain

Opens the **Side-Chain** settings.

### Tube

This versatile compressor with integrated tube-simulation allows you to produce smooth and warm compression effects.



### Input

In combination with the **Output** setting, this parameter determines the compression amount. The higher the input gain setting and the lower the output gain setting, the more compression is applied.

### ATT (0.1 to 100 ms)

Determines how fast the compressor responds. If the attack time is long, more of the initial part of the signal passes through unprocessed.

### REL (10 to 1000 ms)

Sets the time after which the gain returns to its original level. If **Auto Release** is activated, the plug-in automatically finds the best release setting for the audio.

### Drive

Controls the amount of tube saturation.

### Mix

Sets the level balance between the dry signal and the wet signal.

### Output

Sets the output gain.

### Side-Chain

Opens the **Side-Chain** settings.

### Vintage

**Vintage Compressor** is modeled after vintage type compressors.



### Input

In combination with the **Output** setting, this parameter determines the compression amount. The higher the input gain setting and the lower the output gain setting, the more compression is applied.

### ATT (0.1 to 100 ms)

Determines how fast the compressor responds. If the attack time is long, more of the initial part of the signal passes through unprocessed.

### REL (10 to 1000 ms)

Sets the time after which the gain returns to its original level. If **Auto Release** is activated, the plug-in automatically finds the best release setting for the audio material.

### Ratio

Sets the amount of gain reduction that is applied to signals above the set threshold.

### Attack Mode (Punch)

If this option is activated, the early attack phase of the signal is preserved, retaining the original punch in the audio material, even with short **Attack** settings.

### Mix

Sets the level balance between the dry signal and the wet signal.

### Output

Sets the output gain.

### Side-Chain

Opens the **Side-Chain** settings.

## Maximizer



### Optimize

Determines the loudness of the signal.

### Mix

Sets the level balance between the dry signal and the wet signal.

### Output

Sets the output gain.

### RELATED LINKS

[Side-Chain Settings](#) on page 7

## Equalizer

The **Equalizer** module is a high-quality 8-band parametric stereo equalizer with 8 fully parametric mid-range bands. The low and high bands can act as either shelving filter, as peak filter (band-pass), or as cut filter (low-pass/high-pass, band 1 and 8 only).

You can add two **Equalizer** modules to the module chain, **Equalizer A** and **Equalizer B**.



### Band Settings



### On/Off

Activates/Deactivates the corresponding section.

### Channel Settings

Allow you to switch between left/right, stereo, and mid/side processing. In **Left/Right** or **Mid/Side** processing mode, you can make different settings for the two channels.



## IMPORTANT

When using **Mid/Side** processing mode, we recommend that you activate **Linear Phase** in order to avoid unwanted sound colorization.

### Linear Phase

Activates/Deactivates linear phase mode for the corresponding band.

Linear phase mode avoids unwanted frequency dependent phase shifts of the audio signal that might occur with standard minimum phase equalizing.

### NOTE

- Linear phase mode leads to an increase in latency.
- In rare cases, for example, when using low cut filtering with a high slope for bass signals, also an unwanted pre-ringing effect may be audible.

## Equalizer Section



### Type

You can choose between the EQ types **Low Shelf**, **Peak**, **High Shelf**, and **Notch**. For band 1 and 8, you can also select the types **Cut 12**, **Cut 24**, and **Cut 48**.

- **Low Shelf** boosts or attenuates frequencies below the cutoff frequency by the specified amount.
- **High Shelf** boosts or attenuates frequencies above the cutoff frequency by the specified amount.
- **Peak** boosts or attenuates frequencies at the set frequency value with a bell shaped filter.
- **Notch** boosts or attenuates frequencies at the set frequency value with a very narrow filter.
- **Cut** attenuates frequencies below (band 1) or above (band 8) the set frequency. You can choose between different slopes: 6 dB, 12 dB, 24 dB, 48 dB, or 96 dB per octave.

### FREQ (20 to 20000 Hz)

Sets the frequency of the corresponding band.

### Q

Controls the width of the corresponding band.

### Gain (-15 to +15 dB)

Sets the amount of attenuation/boost for the corresponding band.

## Dynamic EQ

**Dynamic EQ** allows you to adjust frequencies and lets you determine when and how the EQ is applied depending on the dynamics of the audio material.

You can add two **Dynamic EQ** modules to the module chain, **Dynamic EQ A** and **Dynamic EQ B**.



### Band Settings



### On/Off

Activates/Deactivates the corresponding section.

### Channel Settings


Allow you to switch between left/right, stereo, and mid/side processing. In **Left/Right** or **Mid/Side** processing mode, you can make different settings for the two channels.

### Equalizer Section



### Type pop-up menu

Allows you to select the EQ types.



- **Low Shelf** boosts or attenuates frequencies below the cutoff frequency by the specified amount.
- **Peak** boosts or attenuates frequencies at the set frequency value with a bell shaped filter.
- **High Shelf** boosts or attenuates frequencies above the cutoff frequency by the specified amount.

**FREQ (20 to 20000 Hz)**

Sets the frequency of the corresponding band.

**Q**

Controls the width of the corresponding band.

**Gain (-15 to +15 dB)**

Sets the amount of attenuation/boost for the corresponding band.

**THRESH (-50 to 0 dB)**

Determines the threshold level. Only signal levels above the threshold are processed.

**ATT (0.1 to 100 ms)**

Determines how fast **Dynamic EQ** responds to signals above the threshold. If the attack time is long, more of the early part of the signal passes through unprocessed.

**REL (10 to 1000 ms)**

Sets the time after which **Dynamic EQ** returns to its original level when the signal drops below the threshold.

**Ratio**

The higher the level of the input signal is above the threshold, the more filtering occurs. Low ratio values mean that the filter starts to boost or attenuate smoothly above the threshold. High ratio values mean that the filter starts to work almost immediately.

**Side-Chain**

Opens the **Side-Chain** settings.


RELATED LINKS

[Side-Chain Settings](#) on page 7

## Saturator

The **Saturator** module allows you to simulate the sound of analog tubes, and the saturation and compression effect when recording on analog tape machines.

You can add two **Saturator** modules to the module chain, **Saturator A** and **Saturator B**.



## Band Settings



### On/Off

Activates/Deactivates the corresponding section.

### Solo Band




Solos the corresponding frequency band.

### Channel Settings

Allow you to switch between left/right, stereo, and mid/side processing. In **Left/Right** or **Mid/Side** processing mode, you can make different settings for the two channels.

### Add/Remove Band

Allow you to add and remove bands.



## Saturator Section



### Tape/Tube

Allows you to switch between tube saturation and tape saturation.

- Tube saturation simulates the saturation of analog tube compressors.
- Tape saturation simulates the saturation and compression effect of analog tape machine recordings.

### Drive

Controls the amount of saturation.

### Mix

Sets the level balance between the dry signal and the wet signal.

### Output

Sets the output gain.

## Imager

The **Imager** module allows you to expand or reduce the stereo width of your audio in up to four bands. This way you can independently adjust the stereo image in defined frequency domains.



## Band Settings



### On/Off

Activates/Deactivates the corresponding section.


### Solo Band



Solos the corresponding frequency band.

### Add/Remove Band

Allow you to add and remove bands.



## Imager Section



### Width

Allows you to control the stereo width per band.

### Pan

Allows you to pan the signal left/right.


### Output

Sets the output level for each band.

## Peak Master

This is a basic plug-in that minimizes peaks in your audio file, allowing a louder mix without clipping. It is useful in taming dynamic instruments.

It is primarily used as a brickwall limiter. For example, you can limit audio peaks without altering the rest of the audio signal. In this case, set **Input Gain** to 0 dB and **Out Ceiling** to 0 dB, to achieve a clip-free audio signal. When used in this way, **Peak Master** is an excellent plug-in to succeed a resampler plug-in, and to proceed a dithering plug-in.



### Input Gain

Values range from -12 dB to 24 dB.

### Out Ceiling

This is the maximum level of the output signal. Values range from -18 dB to 0 dB.

### Softness

This governs the speed at which the signal becomes unaffected after limiting has been triggered on some samples. Values range from -5 to +5.

## RestoreRig


**RestoreRig** allows you to remove noise from an audio recording with different restoration modules. The noise can be an impulsive noise (**DeClicker**), an ambient noise (**DeNoiser**), or a low tonal noise (**DeBuzzer**)




## Main Layout

### Input Signal/Output Signal

Displays the input signal and the output signal of the restored signal. The vertical value scale to the left shows the gain level of the input and output signals. The horizontal scale shows the frequency range.




## Master



The input/output meter provides a peak level meter.

The maximum values for input/output peak level are displayed above the meter display. To reset all maximum values, click any of the values.

## Settings



### Filled Curve

Allows you to fill the curves of the input signal and the output signal.

### Smooth Metering

Determines the reaction time of the display. Lower values result in faster reaction times.



## Gain Control



The **Gain Control** allows you to set the master gain for the modules.

## Modules

The modules **DeClicker**, **DeNoiser**, and **DeBuzzer** allow you to remove different kinds of noises.

- To activate or deactivate a module, click **Activate/Deactivate** on the left of the module name.
- To only listen to the sound that has been removed from the audio, click the **Noise Listening Mode** button of the module that you want to hear.

## DeClicker

**DeClicker** allows you to remove clicks from audio material.



### Activate/Deactivate DeClicker

Activates/Deactivates the module.

### Noise Listening Mode

Allows you to listen to the signal that has been removed from the original audio material.

### Meters

Allow you to monitor the quantity of impulsive noise that is removed from the signal.

#### NOTE

Avoid letting the meter reach the red region, as this can produce destructive artifacts.

---

### Crackle

Allows you to remove very short impulsive noise from the audio signal.

### Click


Allows you to remove medium-sized impulsive noise from the audio signal.

### Pop

Allows you to remove long impulsive noise from the audio signal.

## DeNoiser

**DeNoiser** allows you to remove noise from the audio material.



### Activate/Deactivate DeNoiser

Activates/Deactivates the module.

### Noise Listening Mode

Allows you to listen to the signal that has been removed from the original audio material.

### Dynamic Level

Allows you to remove noise that evolves over time from the audio signal.

### Static Level

Allows you to remove noise that does not evolve over time from the audio signal. The **Learn** option allows you to define the stationary noise.

### Noise

The **Noise** options allow you to define a section in an audio file that contains a static noise that you want to remove. When you then render the audio file, you can remove the recorded static noise from the audio signal.

1. Play back the audio section that contains the noise that you want to remove and click **Learn**.  
**RestoreRig** records the audio for a few seconds to detect the static noise.
2. Use the **Static Level** dial to set the level.
3. To remove the recorded static noise in the audio file, render the audio file.

If you want to record the static noise at another audio section, click **Reset**, play back another audio section, and click **Learn** again.

### Algorithm


Allows you to select different **DeNoiser** algorithms. Depending on the audio material, different modes can affect the **DeNoiser** quality.

- **Smooth** is sufficient for most uses.
- Use **Musical** for harmonic content with low rhythmic or transient components.
- Use **Rhythmic** for drum and percussive content.

- Use **Strong** if the noise level reduction is more important than the accuracy of the noise reduction.
- Use **Speech** for vocal content.

## DeBuzzer

**DeBuzzer** allows you to remove harmonic noise with a fundamental frequency that should be around 50 to 60 Hz.



### Activate/Deactivate DeBuzzer

Activates/Deactivates the module.

### Noise Listening Mode

Allows you to listen to the signal that has been removed from the original audio material.

### Level

Allows you to define the reduction of the noise in dB.

### Sensitivity

Allows you to define how sensitive the reduction will be to the current audio level. At 0 %, **DeBuzzer** reduces the current harmonic noise with the **Level** value. At higher sensitivity values, the level is dynamically defined in a range between 0 dB and the **Level** value. This reduces the buzz when the audio level is low and does not affect the audio when the audio level is high.

### Frequency

Allows you to define the value of the fundamental frequency.

### Auto

If this option is activated, **DeBuzzer** automatically detects the fundamental frequency of the current most prominent harmonic tone.

#### NOTE

Once you have detected the frequency that you want to remove, deactivate **Auto**.

---

## Silence

This plug-in provides a simple way of inserting a precise period of silence at the start or at the end of an audio file. Use this plug-in to add silence at the end of a file, so that the tail of a reverb plug-in does not cut immediately at the end of the file.



### Start

Use the slider to insert from 0 to 60,000 ms of silence at the start of the file.

### End

Use the slider to insert from 0 to 60,000 ms of silence at the end of the file.

## Stereo Expander

This plug-in is a stereo width enhancer that makes a stereo signal sound wider. It gives better results from real stereo material, as opposed to mono channels panned to different positions in the stereo image.



### Width

Higher values result in a greater stereo width. Usually, you set **Width** to values between 0 % and 20 %. Higher values can be used for special effects.

# Steinberg VST 3 Plug-ins

In WaveLab there is no limitation to the use of VST plug-ins. They can be used wherever plug-ins can be inserted.


- You can specify which VST plug-ins should be available in the **Effects** pane and **Final Processing/Dithering** pane of the **Master Section** by using the **Plug-in Settings** dialog.
- VST plug-ins have their own preset handling. You can save or load effect programs (presets).

## AutoPan

This auto-pan effect provides several parameters to modulate the left/right stereo position. You can use presets or create individual curves for the modulation waveform. **AutoPan** also allows for chopping effects by linking the modulation of left and right channel.

### NOTE

The panning effect of this plug-in works only on stereo tracks.



### Waveform display

Shows the shape of the modulation waveform and allows you to manually adjust it. To draw an individual curve, click a node and move the mouse. To draw a straight line, **Shift**-click a node and move the mouse.

### Waveform preset buttons

Allow you to select presets for the modulation waveform.

- **Sine** creates a smooth sweep.

- **Triangle** creates a ramp, that is, a linear movement from full right to full left and back.
- **Square** creates an instant jump to full right, then to full left, and then back to center.
- **Random One Shot** creates a random curve. Click this button again to create a new random curve.
- **Random Continuous** automatically creates a new random curve after each period.

#### Phase

Sets the offset for the starting point of the curve. If multiple **AutoPan** plug-ins are used on different tracks, for example, different offset settings for each track allow for a more organic overall sound.

#### Rate

Sets the auto-pan speed in Hertz and shows the movement within the panorama.

#### Link

If this button is activated, the left and right channel are modulated simultaneously. This results in a chopping effect instead of auto-panning.

In this mode, **Width** sets the intensity of the volume modulation.

#### Width

Sets the amount of deflection to the left and right side of the stereo panorama. If **Link** is activated, this parameter sets the intensity of the volume modulation.

#### Smooth

Allows you to smooth the transition between individual steps of the panorama curve.

## Brickwall Limiter

**Brickwall Limiter** ensures that the output level never exceeds a set limit.



Due to its fast attack time, **Brickwall Limiter** can reduce even short audio level peaks without creating audible artifacts. However, this plug-in creates a latency of 1ms. **Brickwall Limiter** features separate meters for input, output, and the amount of limiting. Position this plug-in at the end of the signal chain, before dithering.

#### Threshold (-20 to 0 dB)

Determines the level where the limiter kicks in. Only signal levels above the set threshold are processed.

### Release (3 to 1000 ms or Auto mode)

Sets the time after which the gain returns to the original level when the signal drops below the threshold. If the **Auto** button is activated, the plug-in automatically finds the best release setting for the audio material.

### Link

If this button is activated, the plug-in uses the channel with the highest level to analyze the input signal. If the button is deactivated, each channel is analyzed separately.

### Detect Intersample Clipping

If this option is activated, the plug-in uses oversampling to detect and limit signal levels between two samples to prevent distortion when converting digital signals into analog signals.


#### NOTE

**Brickwall Limiter** is designed for the reduction of occasional peaks in the signal. If the **Gain Reduction** meter indicates constant limiting, try raising the threshold or lowering the overall level of the input signal.

---

## Channel Extractor

This plug-in allows you to only keep the left or the right channel of a stereo stream.



### Channel

Lets you select whether to keep the left or the right channel of the stereo stream.

## Chorus

This plug-in is a single-stage chorus effect. It doubles the audio that is sent into it with a slightly detuned version.



### Delay

Affects the frequency range of the modulation sweep by adjusting the initial delay time.

### Width

Sets the depth of the chorus effect. Higher settings produce a more pronounced effect.

### Spatial

Sets the stereo width of the effect. Turn clockwise for a wider stereo effect.

### Mix

Sets the level balance between the dry signal and the wet signal. If the effect is used as a send effect, set this parameter to the maximum value, as you can control the dry/effect balance with the send level.

### Rate

Sets the sweep rate.

### Waveform Shape

Allows you to select the modulation waveform, altering the character of the chorus sweep. A sine and a triangle waveform are available.

### Lo Filter/Hi Filter

Allow you to roll off low and high frequencies of the effect signal.

## Compressor

**Compressor** reduces the dynamic range of the audio, making softer sounds louder or louder sounds softer, or both.



**Compressor** features a separate display that graphically illustrates the compressor curve that is shaped according to the **Threshold** and **Ratio** parameter settings. **Compressor** also features a **Gain Reduction** meter that shows the amount of gain reduction in dB, **Soft knee/Hard knee** compression modes, and a program-dependent auto feature for the **Release** parameter.

### Threshold (-60 to 0 dB)

Determines the level where the compressor kicks in. Only signal levels above the set threshold are processed.

### Ratio

Sets the amount of gain reduction applied to signals above the set threshold. A ratio of 3:1 means that for every 3 dB the input level increases, the output level increases by 1 dB.



### Soft Knee

If this button is deactivated, signals above the threshold are compressed instantly according to the set ratio (hard knee). If **Soft Knee** is activated, the onset of compression is more gradual, producing a less drastic result.

### High Ratio

Sets the ratio to a fixed value of 20:1.

### Make-Up (0 to 24 dB or Auto mode)

Compensates for output gain loss caused by compression. If **Auto Make-Up Gain** is activated, the output is automatically adjusted for gain loss.

### Dry Mix

Mixes the dry input signal to the compressed signal.

### Attack (0.1 to 100 ms)

Determines how fast the compressor responds to signals above the set threshold. If the attack time is long, more of the early part of the signal passes through unprocessed.

### Hold (0 to 5000 ms)

Sets the time the applied compression affects the signal after exceeding the threshold. Short hold times are useful for DJ-style ducking, while longer hold times are required for music ducking, for example, when working on a documentary film.

### Release (10 to 1000 ms or Auto mode)

Sets the time after which the gain returns to its original level when the signal drops below the threshold. If **Auto Release** is activated, the plug-in automatically finds the best release setting for the audio material.

### Analysis (Pure Peak to Pure RMS)

Determines whether the input signal is analyzed according to peak or RMS values, or a mixture of both. A value of 0 is pure peak and 100 pure RMS. **RMS** mode operates using the average power of the audio signal as a basis, whereas **Peak** mode operates more on peak levels. As a general guideline, **RMS** mode works better on material with few transients such as vocals, and **Peak** mode works better for percussive material with a lot of transient peaks.

### Live

If this button is activated, the look-ahead feature of the effect is deactivated. Look-ahead produces more accurate processing, but adds a specific amount of latency as a trade-off. If **Live** mode is activated, there is no latency, which is better for live processing.

## CurveEQ

Voxengo **CurveEQ** is a spline equalizer for professional music and audio production applications. **CurveEQ** shows the filter response you are designing by means of a spline, that is, a smooth curvy line. This way you can see how the EQ alters the sound.

**CurveEQ** implements spectrum matching technology that allows you to transfer the spectral shape of one recording to another. In other words, you can copy the frequency balance of existing time-proven mixes so that other mixes can be improved. The filters of **CurveEQ** can be switched between linear-phase and minimum-phase modes. **CurveEQ** also features a customizable spectrum analyzer. Furthermore, you can display, save, and load static spectrum plots for comparison and matching purposes.

For detailed information about **CurveEQ** and its parameters, refer to the documentation provided by Voxengo at <http://www.voxengo.com>.

## DeEsser

**DeEsser** is a special type of compressor that reduces excessive sibilance, primarily for vocal recordings.



You can use it, for example, when close proximity microphone placement and equalizing lead to situations where the overall sound is just right, but where unwanted sibilants occur.

When recording a voice, the position of **DeEsser** in the signal chain is usually after the microphone pre-amp and before a compressor/limiter. This keeps the compressor/limiter from unnecessarily limiting the overall signal dynamics.

### Display

Shows the spectrum of the input signal.

- To adjust the frequency band, drag the border lines or click in the middle of the band and drag.
- To change the width of the frequency band, hold **Shift** and drag to the left or right.

### Filter

#### Lo/Hi

Sets the left and right border of the frequency band. You can set the frequency either in Hz or as a note value. If you enter a note value, the frequency is automatically displayed in Hz accordingly. For example, a note value of A3 sets the frequency to 440 Hz. When you enter a note value, you can also enter a cent offset. For example, enter A5 -23 or C4 +49.

#### NOTE

Make sure that you enter a space between the note and the cent offset. Only in this case, the cent offsets are taken into account.

---

#### Solo

Solos the frequency band. This helps you to find the appropriate position and width of that band.

#### Diff

Plays back what **DeEsser** removed from the signal. This helps you to adjust the frequency band, threshold, and reduction parameters, so that only sharp s-sounds are removed, for example.

### Dynamics

#### Reduction

Controls the intensity of the de-essing effect.

#### Threshold (-50 to 0 dB)

If the **Auto** option is deactivated, you can use this control to set a threshold for the incoming signal level above which the plug-in starts to reduce the sibilants.

#### Release (1 to 1000 ms)

Sets the time after which the de-essing effect returns to zero when the signal drops below the threshold.

#### Auto

Automatically and continually sets an optimum threshold setting independent of the input signal. The **Auto** option does not work for low-level signals (< -30 db peak level). To reduce the sibilants in such a file, set the threshold manually.

### Side-Chain

#### Side-Chain

Activates the internal side-chain filter. You can now shape the input signal according to the filter parameters. Internal side-chaining can be useful for tailoring how the gate operates.

#### Freq (25 Hz to 20 kHz)

If **Side-Chain** is activated, this sets the frequency of the filter. You can set the frequency either in Hz or as a note value. If you enter a note value, the frequency is automatically displayed in Hz accordingly. For example, a note value of A3 sets the frequency to 440 Hz. When you enter a note value, you can also enter a cent offset. For example, enter A5 -23 or C4 +49.

#### NOTE

Make sure that you enter a space between the note and the cent offset. Only in this case, the cent offsets are taken into account.

---

#### Q-Factor

If **Side-Chain** is activated, this sets the resonance or width of the filter.

#### Monitor

Allows you to monitor the filtered signal.

### Live

If this button is activated, the look-ahead feature of the effect is deactivated. Look-ahead produces more accurate processing, but adds a specific amount of latency as a trade-off. If **Live** mode is activated, there is no latency, which is better for live processing.

### Positioning the DeEsser in the Signal Chain

When recording a voice, the position of **DeEsser** in the signal chain is usually located after the microphone pre-amp and before a compressor/limiter. This keeps the compressor/limiter from unnecessarily limiting the overall signal dynamics.

## DeReverb

**DeReverb** allows you to remove reverb from the input signal in real time. The plug-in uses an impulse response that is generated by a physical model based on adjustable parameters and a learning function.



When you activate the learning function, the plug-in records a short range of the input signal and automatically adjusts the parameters of the physical model.

### Frequency display

Sets the spectral envelope of the impulse response. You can edit the four bands of the spectral envelope range and the output level for each band. You can edit the level of a band or the cutoff frequency between two bands by dragging the corresponding handle.

### Algorithm

Sets the restoration algorithm. We recommend to try different algorithms and choose the algorithm that provides the best results.

### Play Mode

Sets the playback mode:

- **Input** plays back the wet input signal.
- **Reverb** plays back only the removed reverb portion.
- **Output** plays back the processed output signal.

### Reduction

Sets the amount of reverb that is removed from the wet input signal.

### IR Physical Model section

#### Duration

Sets the duration of the impulse response.

#### Pre-Delay

Sets a pre-delay for the impulse response.

#### Learn

Activates the learning function.

#### Play IR

Allows you to playback the generated impulse response.

## Distortion

**Distortion** adds crunch to your tracks.



### Boost

Increases the distortion amount.

### Oversampling

Activates/Deactivates oversampling. Oversampling results in less artifacts for higher distortion.

#### NOTE

If this parameter is activated, the effect requires more processing power.

---

### Mix

Sets the level balance between the dry signal and the wet signal.

### Tone

Changes the tonal characteristic of the output signal.

### Feedback

Feeds part of the output signal back to the effect input. Higher settings increase the distortion effect.

### Spatial


Changes the distortion characteristics of the left and right channels, thus creating a stereo effect.

### Output

Sets the output level.

## DualFilter

**DualFilter** filters out specific frequencies while allowing others to pass through.



### Position

Sets the filter cutoff frequency. If you set this to a negative value, **DualFilter** acts as a low-pass filter. Positive values cause **DualFilter** to act as a high-pass filter.

### Resonance

Sets the sound characteristic of the filter. With higher values, a ringing sound is heard.

## EnvelopeShaper

**EnvelopeShaper** can be used to attenuate or boost the gain of the attack and release phase of audio material.

You can use the knobs or drag the breakpoints in the graphical display to change parameter values. Be careful with levels when boosting the gain and if needed reduce the output level to avoid clipping.



#### Attack (-20 to 20 dB)

Sets the gain of the attack phase of the signal.

#### Length (5 to 200 ms)

Sets the length of the attack phase.

#### Release

Sets the gain of the release phase of the signal.

#### Output

Sets the output level.

## Expander

**Expander** reduces the output level in relation to the input level for signals below the set threshold. This is useful if you want to enhance the dynamic range or reduce the noise in quiet passages.

You can either use the knobs or drag the breakpoints in the graphical display to change the **Threshold** and the **Ratio** parameter values.



### **Threshold**

Determines the level where the expansion kicks in. Only signal levels below the set threshold are processed.

### **Ratio**

Sets the amount of gain boost applied to signals below the threshold.

### **Soft Knee**

If this button is deactivated, signals below the threshold are expanded instantly according to the set ratio (hard knee). If **Soft Knee** is activated, the onset of expansion is more gradual, producing less drastic results.

### **Fall (0.1 to 100 ms)**

Determines how fast the expander responds to signals below the set threshold. If the fall time is long, more of the early part of the signal passes through unprocessed.

### **Hold (0 to 2000 ms)**

Sets the time the applied expansion affects the signal below the threshold.

### **Rise (10 to 1000 ms or Auto mode)**

Sets the time after which the gain returns to its original level when the signal exceeds the threshold. If the **Auto Rise** button is activated, the plug-in automatically finds the best rise setting for the audio material.

### **Analysis (Pure Peak to Pure RMS)**

Determines whether the input signal is analyzed according to peak or RMS values, or a mixture of both. A value of 0 is pure peak and 100 pure RMS. **RMS** mode operates using the average power of the audio signal as a basis, whereas **Peak** mode operates more on peak levels. As a general guideline, **RMS** mode works better on material with few transients such as vocals, and **Peak** mode works better for percussive material with a lot of transient peaks.

### **Live**

If this button is activated, the look-ahead feature of the effect is deactivated. Look-ahead produces more accurate processing, but adds a specific amount of latency as a trade-off. If **Live** mode is activated, there is no latency, which is better for live processing.

## **Frequency 2**

**Frequency 2** is a high-quality equalizer with 8 fully parametric bands. The bands can act as shelving filter, as peak or notch filter (band-pass), or as cut filter (low-pass/high-pass).

The plug-in supports separate internal or external side-chaining for each band. For **Low Shelf**, **High Shelf**, and **Peak** filters, dynamic filtering lets you determine when and how the EQ is applied, depending on the dynamics of the audio material.





## Main Section

### Reset



**Alt/Opt**-click this button to reset all parameter values.

### Auto Listen for Filters



If this option is activated and you edit a parameter of a band, the corresponding frequency range is isolated. This helps you to focus on a particular frequency range and allows you to locate unwanted frequencies in your audio.

### Global Settings



Opens the settings dialog for the spectrum display.

### Keys

Shows/Hides the keyboard below the graphical editor.

On the keyboard, color indicators reflect the center frequencies of all active equalizer bands. You can adjust the frequency of a band by dragging its color indicator. If you drag the color indicator of a band to a key, the band is set to its exact frequency.

### View

Toggles between single-band and multi-band view. Single-band view provides additional parameters for each band.

#### NOTE

To toggle between single-band and multi-band view, you can also double-click on the top of a band section.

### Output

Adjusts the overall output level.


### Output meter

Shows the level of the overall output signal.

## Band Settings



Multi-band view



Single-band view

### Activate/Deactivate Band

Activates/Deactivates the corresponding band.

#### NOTE

- To activate/deactivate a band, you can also double-click the corresponding handle in the graphical editor.
- You can modify the parameters of deactivated bands.

### Switch Processing buttons

Allow you to switch between left/right, stereo, and mid/side processing. In **Left/Right** or **Mid/Side** processing mode, you can make different settings for the two channels.

#### IMPORTANT

When using **Mid/Side** processing mode, we recommend that you activate **Linear Phase Processing** in order to avoid unwanted sound colorization.

NOTE

This setting is only available for stereo tracks.

---

### Linear Phase Processing

Activates/Deactivates linear phase mode for the corresponding band.

Linear phase mode avoids unwanted frequency-dependent phase shifts of the audio signal that might occur with standard minimum phase equalizing.

Activating this option deactivates dynamic filtering for the corresponding band.

NOTE

- Linear phase mode leads to an increase in latency.
  - In rare cases, for example, when using low-cut filtering with a high slope for bass signals, you may hear an unwanted pre-ringing effect.
- 

### Filter type

You can choose between the filter types **Low Shelf**, **Peak**, **High Shelf**, and **Notch**. For band 1 and 8, you can also select the types **Cut 6**, **Cut 12**, **Cut 24**, **Cut 48**, and **Cut 96**.

- **Low Shelf** boosts or attenuates frequencies below the cutoff frequency by the specified amount.
- **Peak** boosts or attenuates frequencies at the set frequency value with a bell-shaped filter.
- **High Shelf** boosts or attenuates frequencies above the cutoff frequency by the specified amount.
- **Notch** boosts or attenuates frequencies at the set frequency value with a very narrow filter.
- **Cut** attenuates frequencies below (band 1) or above (band 8) the set frequency. You can choose between different slopes: 6 dB, 12 dB, 24 dB, 48 dB, or 96 dB per octave.

### Freq

Sets the frequency of the corresponding band. You can set the frequency either in Hz or as a note value. If you enter a note value, the frequency is automatically changed to Hz. For example, a note value of A3 sets the frequency to 440 Hz. When you enter a note value, you can also enter a cent offset. For example, enter A5 -23 or C4 +49.

NOTE

- You can adjust the **Freq** parameter of a band in the graphical editor by clicking the corresponding handle and moving the mouse left and right.
  - Ensure that you enter a space between the note and the cent offset. Only in this case, the cent offsets are taken into account.
- 

If the band is active, the frequency value is reflected as a highlighted key on the keyboard below the graphical editor.

### Q

For **Peak** and **Notch** filters, this parameter controls the width of the band. For **Low Shelf** and **High Shelf** filters, it adds a drop or a boost, depending on the gain setting of the band.

**NOTE**

- You can adjust the **Q** parameter of a band in the graphical editor by **⌘**-clicking the corresponding handle and moving the mouse up and down. Alternatively, you can point on the handle and turn the mouse wheel.
  - This parameter is not available for **Cut** filters.
- 

**Gain**

Sets the amount of attenuation/boost for the corresponding band. If **Dynamic Filtering** is activated, this is also the target gain value.

**NOTE**

- You can adjust the **Gain** parameter of a band in the graphical editor by **Ctrl/Cmd**-clicking the corresponding handle and moving the mouse up and down.
  - This parameter is not available for **Cut** filters.
- 

**Invert Gain**

Inverts the value of the gain parameter. Positive gain values become negative and vice versa.

**Show Dynamics Parameters**

Shows/Hides parameters for dynamic filtering in multi-band view.

**NOTE**

This setting is only available for the filter types **Low Shelf**, **Peak**, and **High Shelf**.

---

**Activate/Deactivate Dynamic Filtering**

Activates/Deactivates dynamic filtering for the corresponding band. If this option is activated, the filtering of the band depends on the dynamics of the input signal. Activating this setting deactivates linear phase mode for the corresponding band.

**NOTE**

This setting is only available for the filter types **Low Shelf**, **Peak**, and **High Shelf**.

---

**Threshold**

Determines the threshold level. Only signal levels above the threshold are dynamically filtered.

**Input meter**

Shows the level of the input signal.

**NOTE**

In multi-band view, the input level meter is combined with the threshold handle.

---

**Start**

Allows you to adjust the starting point for the gain. Dynamic filtering takes place from this point to the set **Gain** of the EQ band.

**NOTE**

This setting is only available in single-band view.

---

### Ratio

The higher the level of the input signal is above the threshold, the more filtering occurs. Low ratio values mean that the filter starts to boost or attenuate smoothly above the threshold. High ratio values mean that the target gain is reached almost immediately.

### Attack

Determines how fast the dynamic EQ responds to signals above the threshold. If the attack time is long, more of the early part of the signal passes through unprocessed.

### Release

Sets the time after which the dynamic EQ returns to its original level when the signal drops below the threshold.

### Side-Chain

Activates/Deactivates internal side-chaining for the corresponding band. This allows you to shape the input signal according to the side-chain filter parameters.

#### NOTE

- This setting is only available in single-band view.
  - Side-chaining is only available if dynamic filtering is activated.
  - If side-chaining is activated, this is indicated by showing **SC** on the top of a band section.
- 

### Side-Chain Filter Auto

Activates/Deactivates automatic filtering of the side-chain signal. If this parameter is activated, the **SC Freq** and **SC Q** parameters are deactivated. Instead, the **Freq** and **Q** values of the corresponding band are used.

#### NOTE

This setting is only available in single-band view.

---

### Side-Chain Filter Listen

Allows you to solo the side-chain filter. This way, you can quickly check the part of the signal that is filtered out using the current settings.

#### NOTE

This setting is only available in single-band view.

---

### SC Freq

Sets the frequency of the side-chain filter for the corresponding band. You can set the frequency either in Hz or as a note value. If you enter a note value, the frequency is automatically changed to Hz. For example, a note value of A3 sets the frequency to 440 Hz. When you enter a note value, you can also enter a cent offset. For example, enter A5 -23 or C4 +49.

#### NOTE

- Ensure that you enter a space between the note and the cent offset. Only in this case, the cent offsets are taken into account.
  - This setting is only available in single-band view.
-

### SC Q

Sets the resonance or width of the filter for the corresponding band.

#### NOTE

This setting is only available in single-band view.

---

## Global Settings

- To open the **Global Settings**, click **Global Settings**  above the spectrum display.

### Spectrum Display

#### Show Spectrum

Activates/Deactivates the spectrum display.

#### Peak Hold

Holds the peak values of the spectrum display for a short time.

#### Smooth

Determines the reaction time of the spectrum display. Lower values result in faster reaction times and smoother transitions.

#### Bar Graph

If this option is activated, the frequency spectrum is analyzed into 60 separate bands that are displayed as vertical bars.

#### Two Channels

If this option is activated, the spectrums of the left and right channels are displayed separately.

#### Slope

Tilts the spectrum display around the 1 kHz pivot.

### EQ Curve

#### Show Curve

Shows/Hides the EQ curve in the spectrum display.

#### Filled

If this option is activated, the EQ curve is filled. **Amount** allows you to specify the degree of coverage between 10 and 80 %.

## Gate

Gating, or noise gating, silences audio signals below a set threshold. As soon as the signal level exceeds the threshold, the gate opens to let the signal through.



### Attack (0.1 to 1000 ms)

Sets the time after which the gate opens when it is triggered.

#### NOTE

Deactivate the **Live** button to make sure that the gate is already open when a signal above the threshold is played back.

### Hold (0 to 2000 ms)

Determines how long the gate remains open after the signal drops below the threshold level.

### Release (10 to 1000 ms or Auto mode)

Sets the time after which the gate closes after the set **Hold** time. If **Auto Release** is activated, the plug-in automatically finds the best release setting for the audio material.

### Threshold

Determines the level at which the gate is activated. Signal levels above the set threshold trigger the gate to open, and signal levels below the set threshold close the gate.

### State LED

Indicates whether the gate is open (LED lights up in green), closed (LED lights up in red), or in an intermediate state (LED lights up in yellow).

### Analysis (Pure Peak to Pure RMS)

Determines whether the input signal is analyzed according to peak or RMS values, or a mixture of both. A value of 0 is pure peak and 100 pure RMS. **RMS** mode operates using the average power of the audio signal as a basis, whereas **Peak** mode operates more on peak levels. As a general guideline, **RMS** mode works better on material with few transients such as vocals, and **Peak** mode works better for percussive material with a lot of transient peaks.

### Range

Adjusts the attenuation of the gate when it is shut. If **Range** is set to minus infinite **-∞**, the gate is completely shut. The higher the value, the higher the level of the signal that passes through the shut gate.

### Live

If this button is activated, the look-ahead feature of the effect is deactivated. Look-ahead produces more accurate processing, but adds a specific amount of latency as a trade-off. If **Live** mode is activated, there is no latency, which is better for live processing.

## Side-Chain Section

### Side-Chain

Activates the internal side-chain filter. The input signal can then be shaped according to the filter parameters. Internal side-chaining is useful for tailoring how the gate operates.

### Monitor

Allows you to monitor the filtered signal.

### Center

If **Side-Chain** is activated, this sets the center frequency of the filter.


### Q-Factor

If **Side-Chain** is activated, this sets the resonance or width of the filter.

### Filter Type (Low-Pass/Band-Pass/High-Pass)

If **Side-Chain** is activated, these buttons allow you to set the filter type to low-pass, band-pass, or high-pass.

## GEQ-10/GEQ-30



GEQ-30





GEQ-30

Each band can be attenuated or boosted by up to 12 dB, allowing for fine control of the frequency response. In addition, there are several preset modes available that can add color to the sound of **GEQ-10**.

You can draw response curves in the main display by clicking and dragging with the mouse. You have to click one of the sliders before you drag across the display.

At the bottom of the window, the individual frequency bands are shown in Hz. At the top of the display, the amount of attenuation/boost is shown in dB.

#### **Output**

Sets the overall gain of the equalizer.

#### **Flatten**

Resets all the frequency bands to 0 dB.

#### **Range**

Allows you to adjust how much a set curve cuts or boosts the signal.

#### **Invert**

Inverts the current response curve.

#### **Mode pop-up menu**

Allows you to set the filter mode that determines how the various frequency band controls interact to create the response curve.

### **EQ Modes**

The **Mode** pop-up menu in the lower right corner allows you to select an EQ mode, which add color or character to the equalized output in various ways.

#### **True Response**

Applies serial filters with an accurate frequency response.

#### **Digital Standard**

In this mode, the resonance of the last band depends on the sample rate.

#### **Classic**

Applies a classic parallel filter structure where the response does not follow the set gain values accurately.

#### **VariableQ**

Applies parallel filters where the resonance depends on the amount of gain.

### ConstQ asym

Applies parallel filters where the resonance is raised when boosting the gain and vice versa.

### ConstQ sym

Applies parallel filters where the resonance of the first and last bands depends on the sample rate.

### Resonant

Applies serial filters where a gain increase of one band lowers the gain in adjacent bands.

## Imager

**Imager** allows you to expand or reduce the stereo width of your audio in up to 4 bands. This way, you can independently adjust the stereo image in defined frequency domains.



### Bands

Sets the number of frequency bands.

### Live

If this button is activated, a more analog-style filter bank is used. This mode introduces no latency and is better suited for live performances. If this button is deactivated, a more neutral-sounding linear phase filter bank is used, at the cost of introducing latency.

### Frequency display

Shows a spectrum display and allows you to edit the band range and the output level for each band.

You can edit the output level of a band or the cutoff frequency between two bands by dragging the corresponding handle.

### **Output meter**

Shows the level of the overall output signal.

### **Activate/Deactivate Band**

Activates/Deactivates the corresponding frequency band.

### **Solo Band**



Solos the corresponding frequency band.

### **Phase display**

A phase scope for each band indicates the phase and amplitude relationship between the stereo channels. The phase scope works as follows:

- A vertical line indicates a perfect mono signal (the left and right channels are the same).
- A horizontal line indicates that the left channel is the same as the right, but with an inverse phase.
- A fairly round shape indicates a well balanced stereo signal. If the shape leans to one side, there is more energy in the corresponding channel.
- A perfect circle indicates a sine wave on one channel, and the same sine wave shifted by 45° on the other.

Generally, the more you can see a thread, the more bass is in the signal, and the more spray-like the display, the more high frequencies are in the signal.

The phase correlation meters below work as follows:

- The vertical bar shows the current phase correlation.
- With a mono signal, the meter shows +1, indicating that both channels are perfectly in phase.
- If the meter shows -1, the two channels are the same, but one is inverted.

### **Show/Hide Phase Scope**



Shows/Hides the phase scopes and phase correlation meters for all bands.

### **Width**

Sets the stereo width for the corresponding band.

### **Pan**

Sets the left-right panning for the corresponding band.

### **Output**

Sets the output level for the corresponding band.

## Limiter

**Limiter** is designed to ensure that the output level never exceeds a set output level, to avoid clipping in following devices.



**Limiter** can adjust and optimize the **Release** parameter automatically according to the audio material, or it can be set manually. **Limiter** features separate meters for the input, output and the amount of limiting (middle meters).

### Input (-24 to 24 dB)

Sets the input gain.

### Release (0.1 to 1000 ms or Auto mode)

Sets the time after which the gain returns to its original level. If **Auto Release** is activated, the plug-in automatically finds the best release setting for the audio material.

### Output

Sets the maximum output level.

## L/R to M/S, M/S to L/R

This plug-in allows you to convert a stereo signal into a M/S signal and vice versa.

The **L/R to M/S** tool converts a L/R signal that is divided into a left and a right signal into a M/S signal that is divided into a mid signal (L+R) and side signals (L-R).

The **M/S to L/R** tool reconverts the M/S signal into a L/R signal.

## Magneto II

**Magneto II** simulates the saturation and compression of recording on analog tape machines.



### Saturation

Determines the amount of saturation and the generation of overtones. This leads to a small increase in input gain.

### Saturation On/Off

Activates/Deactivates the saturation effect.

### Dual Mode

Simulates the use of two machines.

### Frequency Range Low/High

These parameters set the frequency range of the spectrum band to which the tape effect is applied.

For example, to avoid the saturation of lower frequencies, set the **Low** value to 200 Hz or 300 Hz. To avoid the saturation of very high frequencies, set the **High** parameter to values below 10 kHz.

### Solo

Allows you to hear only the set frequency range including the tape simulation effect. This helps you to determine the appropriate frequency range.

### HF-Adjust

Sets the amount of high frequency content of the saturated signal.

### HF-Adjust On/Off

Activates/Deactivates the **HF-Adjust** filter.

## Maximizer

**Maximizer** raises the loudness of audio material without the risk of clipping. The plug-in provides two modes, **Classic** and **Modern**, that offer different algorithms and parameters.



### Classic

**Classic** mode provides the classic algorithms from previous versions of this plug-in. This mode is suited for all styles of music.

### Modern

In **Modern** mode, the algorithm allows for more loudness than in **Classic** mode. This mode is particularly suited for contemporary styles of music.

**Modern** mode also provides additional settings to control the release phase:

- **Release** sets the overall release time.
- **Recover** allows for a faster signal recovering at the beginning of the release phase.

### Optimize

Determines the loudness of the signal.

### Mix

Sets the level balance between the dry signal and the wet signal.

### Output

Sets the maximum output level.

### Soft Clip

If this button is activated, **Maximizer** starts limiting or clipping the signal softly. At the same time, harmonics are generated, adding a warm, tube-like characteristic to the audio material.

## Mix6to2

**Mix6to2** lets you quickly mix down your surround mix format to stereo. You can control the levels of up to six surround channels and decide for each channel up to which level it is included in the resulting mix.

### NOTE

This plug-in does not simulate a surround mix or add any psycho-acoustical artifacts to the resulting output – it is simply a mixer. The plug-in is only available in the **Master Section** and if a surround audio montage is active.

---



### Surround Channels

#### Volume faders

Determine how much of the signal is included in the left and/or right channel of the output bus.

#### Link

Links the volume faders of a surround channel.

#### Invert Phase

Inverts the phase of the corresponding surround bus channel.

### Output Bus

#### Volume faders

Set the volume of the mixed output.

#### Link

Links the **Output** faders.

#### Normalize

If this option is activated, the mixed output is normalized. For example, the output level is automatically adjusted so that the loudest signal is as loud as possible without clipping.

## Mix8to2

**Mix8to2** lets you quickly mix down your surround mix format to stereo. You can control the levels of up to eight surround channels and decide for each channel up to which level it is included in the resulting mix.

### NOTE

This plug-in does not simulate a surround mix or add any psycho-acoustical artifacts to the resulting output – it is simply a mixer. The plug-in is only available in the **Master Section** and if a 8 channel audio montage is active.



### Surround Channels

#### Volume faders

Determine how much of the signal is included in the left and/or right channel of the output bus.

#### Link

Link the volume faders.

#### Invert Phase

Inverts the phase of the corresponding surround bus channel.

### Output Bus

#### Volume faders

Set the volume of the mixed output.

#### Link

Links the **Output** faders.


#### Normalize

If this option is activated, the mixed output is normalized. For example, the output level is automatically adjusted so that the loudest signal is as loud as possible without clipping.



## MonoDelay

This is a mono delay effect. The delay line uses freely specified delay time settings.



### Lo Filter

Affects the feedback loop of the effect signal and allows you to roll off low frequencies. The button below the knob activates/deactivates the filter.

### Hi Filter

Affects the feedback loop of the effect signal and allows you to roll off high frequencies. The button below the knob activates/deactivates the filter.

### Delay

Sets the delay time in milliseconds.

### Feedback

Sets the amount of the signal that is sent back into the delay input. The higher this value, the higher the number of repeats.

### Mix

Sets the level balance between the dry signal and the wet signal. If the effect is used as a send effect, set this parameter to the maximum value, as you can control the dry/effect balance with the send level.

## MonoToStereo

**MonoToStereo** turns a mono signal into a pseudo-stereo signal. The plug-in can be used on a mono file or a stereo file with equal channels.

### NOTE

This plug-in works only on stereo tracks.

---



### Delay

Increases the amount of differences between the left and right channels to further increase the stereo effect.

### Width

Controls the width or depth of the stereo enhancement. Turn clockwise to increase the enhancement.

### Mono

Switches the output to mono, to check for possible unwanted coloring of the sound which sometimes can occur when creating an artificial stereo image.

### Color

Generates additional differences between the channels to increase the stereo enhancement.

## MultibandCompressor

**MultibandCompressor** allows a signal to be split into four frequency bands. You can specify the level, bandwidth, and compressor characteristics for each band.



### NOTE

To compensate for output gain loss that is caused by compression, **MultibandCompressor** uses an automatic make-up gain. If side-chaining is activated for a frequency band in the side-chain section, the automatic make-up gain is deactivated for this band.

---

## Frequency Band Editor

The frequency band editor in the upper half of the panel is where you set the width of the frequency bands as well as their level after compression. The vertical value scale to the left shows the gain level of each frequency band. The horizontal scale shows the available frequency range.

- To define the frequency range of the different frequency bands, use the handles at the sides of each frequency band.
- To attenuate or boost the gain of the frequency bands by  $\pm 15$  dB after compression, use the handles at the top of each frequency band.

### Live

If this button is activated, the look-ahead feature of the effect is deactivated. Look-ahead produces more accurate processing, but adds a specific amount of latency as a trade-off. If **Live** mode is activated, there is no latency, which is better for live processing.

### Bypass Band



Bypasses a frequency band.

### Solo Band



Solos the corresponding frequency band.

### Output (-24 to 24 dB)

Sets the output level.

## Compressor Section

You can specify the **Threshold** and **Ratio** by moving breakpoints or using the corresponding knobs. The threshold is marked by the first breakpoint where the line deviates from the straight diagonal.

### Threshold (-60 to 0 dB)

Determines the level where the compressor kicks in. Only signal levels above the set threshold are processed.

### Ratio

Sets the amount of gain reduction applied to signals above the set threshold. A ratio of 3:1 means that for every 3 dB the input level increases, the output level increases by 1 dB.

### Attack (0.1 to 100 ms)

Determines how fast the compressor responds to signals above the set threshold. If the attack time is long, more of the early part of the signal passes through unprocessed.

### Release (10 to 1000 ms or Auto mode)

Sets the time after which the gain returns to its original level when the signal drops below the threshold. If **Auto Release** is activated, the plug-in automatically finds the best release setting for the audio material.

## Side-Chain Section

To open the side-chain section, click the **SC** button at the bottom left of the plug-in window.

## IMPORTANT

To be able to use the side-chain function for the bands, global side-chain must be activated for the plug-in.

---



### Side-Chain

Activates the internal side-chain filter. The side-chain signal can then be shaped according to the filter parameter.

### Frequency

If **Side-Chain** is activated, this sets the frequency of the side-chain filter.

### Q-Factor

If **Side-Chain** is activated, this sets the resonance or width of the filter.

### Monitor

Allows you to monitor the filtered signal.

## MultibandEnvelopeShaper

**MultibandEnvelopeShaper** allows a signal to be split into four frequency bands. You can attenuate or boost the gain of the attack and release phase of audio material for each band.



### Frequency Band Editor

The frequency band editor in the upper half of the panel is where you set the width of the frequency bands as well as their level. The vertical value scale to the left shows the gain level of each frequency band. The horizontal scale shows the available frequency range.

- To define the frequency range of the different frequency bands, use the handles at the sides of each frequency band.
- To attenuate or boost the gain of the frequency band, use the handles at the top of each frequency band.

### Live

If this button is activated, the look-ahead feature of the effect is deactivated. Look-ahead produces more accurate processing, but adds a specific amount of latency as a trade-off. If **Live** mode is activated, there is no latency, which is better for live processing.

### Bypass Band



Bypasses a frequency band.

### Solo Band



Solos the corresponding frequency band.

**Output (-24 to 24 dB)**

Sets the output level.

**Shaper Section**

You can specify the **Attack**, **Length**, and **Release** by moving breakpoints or using the corresponding knobs. Be careful with levels when boosting the gain. You can reduce the output level to avoid clipping.

**Attack (-20 to 20 dB)**

Sets the gain of the attack phase of the signal.

**Length (5 to 200 ms)**

Sets the length of the attack phase.

**Release**

Sets the gain of the release phase of the signal.

**Sensitivity (-40 to -10 dB)**

Sets the sensitivity of the detection.

**Output**

Sets the output level.

## MultibandExpander

**MultibandExpander** allows a signal to be split into four frequency bands. You can reduce the output level in relation to the input level for signals below the set threshold for each band. This is useful if you want to enhance the dynamic range or reduce the noise in quiet passages.



### Frequency Band Editor

The frequency band editor in the upper half of the panel is where you set the width of the frequency bands as well as their level after expansion. The vertical value scale to the left shows the gain level of each frequency band. The horizontal scale shows the available frequency range.

- To define the frequency range of the different frequency bands, use the handles at the sides.
- To attenuate or boost the gain of the frequency band after expansion, use the handles on top of each frequency band.

### Live

If this button is activated, the look-ahead feature of the effect is deactivated. Look-ahead produces more accurate processing, but adds a specific amount of latency as a trade-off. If **Live** mode is activated, there is no latency, which is better for live processing.

### Bypass Band



Bypasses a frequency band.

### Solo Band



Solos the corresponding frequency band.

### Output (-24 to 24 dB)

Sets the output level.

## Expander Section

You can specify the **Threshold** and **Ratio** by moving breakpoints or using the corresponding knobs. The first breakpoint from which the line deviates from the straight diagonal is the threshold point.

### Threshold

Determines the level where the expansion kicks in. Only signal levels below the set threshold are processed.

### Ratio

Sets the amount of gain boost applied to signals below the threshold.

### Maximum Reduction

Sets the maximum amount by which the level is reduced when the signal falls below the set threshold.

### Fall (0.1 to 100 ms)

Determines how fast the expander responds to signals below the set threshold. If the fall time is long, more of the early part of the signal passes through unprocessed.

### Hold (0 to 2000 ms)

Sets the time the applied expansion affects the signal below the threshold.

### Rise (10 to 1000 ms or Auto mode)

Sets the time after which the gain returns to its original level when the signal exceeds the threshold. If the **Auto Rise** button is activated, the plug-in automatically finds the best rise setting for the audio material.

### Output

Sets the output level.

## Side-Chain Section



### Side-Chain

Activates the internal side-chain filter. The side-chain signal can then be shaped according to the filter parameters. Side-chaining is useful for tailoring how the effect operates.

### Frequency

If **Side-Chain** is activated, this sets the frequency of the side-chain filter.



### Q-Factor

If **Side-Chain** is activated, this sets the resonance or width of the filter.

### Monitor

Allows you to monitor the filtered signal.

## Octaver

This plug-in can generate two additional voices that track the pitch of the input signal one octave and two octaves below the original pitch. **Octaver** is best used with monophonic signals.



### Direct

Sets the level balance between the dry signal and the wet signal. A value of 0 means that only the generated and transposed signal is heard. By raising this value, more of the original signal is heard.

### Octave 1

Adjusts the level of the generated signal one octave below the original pitch. A setting of 0 means that the voice is muted.

### Octave 2

Adjusts the level of the generated signal two octaves below the original pitch. A setting of 0 means that the voice is muted.

## PingPongDelay

This is a stereo delay effect that alternates each delay repeat between the left and right channels.

### NOTE

This plug-in works only on stereo tracks.



**Lo Filter**

Affects the feedback loop of the effect signal and allows you to roll off low frequencies. The button below the knob activates/deactivates the filter.

**Hi Filter**

Affects the feedback loop of the effect signal and allows you to roll off high frequencies. The button below the knob activates/deactivates the filter.

**Delay**

Sets the delay time in milliseconds.

**Feedback**

Sets the amount of the signal that is sent back into the delay input. The higher this value, the higher the number of repeats.

**Mix**

Sets the level balance between the dry signal and the wet signal. If the effect is used as a send effect, set this parameter to the maximum value, as you can control the dry/effect balance with the send level.

**Spatial**

Sets the stereo width for the left/right repeats. Turn clockwise for a more pronounced stereo ping-pong effect.

**Start Left/Start Right**

Determines whether the delay repeat starts on the left or the right channel.

## PostFilter

This effect allows quick and easy filtering of unwanted frequencies, creating room for the important sounds in your mix.



**PostFilter** combines a low-cut filter, a notch filter, and a high-cut filter. You can change the settings by dragging the curve points in the graphical display, or by adjusting the controls below the display section.

### Graphical display

Visualizes the settings for all parameters.

### Level meter

Shows the output level, giving you an indication of how the filtering affects the overall level of the edited audio.

### Low-Cut Freq (20 Hz to 1 kHz, or Off)

Allows you to eliminate low-frequency noise. The filter is inactive if the curve point is located all the way to the left. You can set the frequency either in Hz or as a note value. If you enter a note value, the frequency is automatically changed to Hz. For example, a note value of A3 sets the frequency to 440 Hz. When you enter a note value, you can also enter a cent offset. For example, enter A5 -23 or C4 +49.

#### NOTE

Ensure that you enter a space between the note and the cent offset. Only in this case, the cent offsets are taken into account.

### Low-Cut Slope

Allows you to choose a slope value for the low-cut filter.

### Low-Cut Preview

Use this button between the **Low-Cut** controls and the graphical display to switch the filter to a complementary high-cut filter. This deactivates any other filters, allowing you to listen only to the frequencies that you want to filter out.

### Notch Freq

Sets the frequency of the notch filter. You can set the frequency either in Hz or as a note value. If you enter a note value, the frequency is automatically changed to Hz. For example, a note value of A3 sets the frequency to 440 Hz. When you enter a note value, you can also enter a cent offset. For example, enter A5 -23 or C4 +49.

#### NOTE

Ensure that you enter a space between the note and the cent offset. Only in this case, the cent offsets are taken into account.

---

### Notch Gain

Adjusts the gain of the selected frequency. Use positive values to identify the frequencies that you want to filter out.

### Notch Gain Invert

This button inverts the gain value of the notch filter. Use this button to filter out unwanted noise. When looking for the frequency to omit, it sometimes helps to boost it first (set the notch filter to positive gain). After you have found the frequency of the noise, you can use the **Invert** button to cancel it out.

### Notch Q-Factor

Sets the width of the notch filter.

### Notch Preview

Use this button between the notch filter controls and the graphical display to create a band-pass filter with the peak filter's frequency and Q. This deactivates any other filters, allowing you to listen only to the frequencies you want to filter out.

### Notches buttons (1, 2, 4, 8)

These buttons add additional notch filters to filter out harmonics.

### High-Cut Freq (3 Hz to 20 kHz, or Off)

This high-cut filter allows you to remove high-frequency noise. The filter is inactive if the curve point is located all the way to the right. You can set the frequency either in Hz or as a note value. If you enter a note value, the frequency is automatically changed to Hz. For example, a note value of A3 sets the frequency to 440 Hz. When you enter a note value, you can also enter a cent offset. For example, enter A5 -23 or C4 +49.

#### NOTE

Ensure that you enter a space between the note and the cent offset. Only in this case, the cent offsets are taken into account.

---

### High-Cut Slope

Allows you to choose a slope value for the high-cut filter.

### High-Cut Preview

This button between the **High-Cut** controls and the graphical display allows you to switch the filter to a complementary low-cut filter. This deactivates any other filters, allowing you to listen only to the frequencies you want to filter out.

## Quadrafuzz v2

**Quadrafuzz v2** is a multi-band distortion and multi-effect plug-in for processing drums and loops but also for treatment of vocals, for example. You can distort up to 4 bands. 5 different distortion modes with several sub-modes are available.



### Frequency Band Editor

The frequency band editor in the upper half of the panel is where you set the width of the frequency bands as well as the output level. The vertical value scale to the left shows the gain level of each frequency band. The horizontal scale shows the available frequency range.

- To define the frequency range of the different frequency bands, use the handles at the sides of each frequency band.
- To attenuate or boost the output level of each frequency band by  $\pm 15$  dB, use the handles on top of each frequency band.

### Global Settings

#### SB

Switches between multi band and single band mode.

#### Scenes

You can save up to 8 different settings. If the default setting of a scene is active, the selected scene button lights up yellow.

If you change the default settings, the button lights up green, indicating that this scene has customized settings.



To copy the settings of a scene to another scene, select the scene that you want to copy, click **Copy**, and click one of the numbered buttons.

You can automate the selection of scenes.

### Mix

Sets the level balance between the dry signal and the wet signal.

### Output (-24 to 24 dB)

Sets the output level.

## Band Settings

### Mute Band



Mutes/Unmutes a frequency band.

### Bypass Band



Bypasses a frequency band.

### Solo Band



Solos the corresponding frequency band.

### In/Out meter

Display the input and output level.

### Gate

Determines the level at which the gate is activated. Signal levels above the set threshold trigger the gate to open, and signal levels below the set threshold close the gate.

## Tape

This band mode simulates the saturation and compression of recording on analog tape machines.

### Drive

Controls the amount of tape saturation.

### Tape Mode Dual

Simulates the use of two machines.

## Tube

This band mode simulates the saturation effects using analog tubes.

### Drive

Controls the amount of tube saturation.

### **Tubes**

Determine the number of tubes that are simulated.

### **Dist**

This band mode adds distortion to your tracks.

### **Drive**

Controls the amount of distortion.

### **FBK**

Feeds part of the output signal back to the effect input. Higher settings increase the distortion effect.

## **Amp**

This band mode simulates the sound of various types of guitar amps.

### **Drive**

Controls the amount of amp overdrive.

### **Amp Types**

You can select the following types of guitar amps:

- Amp Clean
- Amp Crunch
- Amp Lead

## **Dec**

This band mode allows you to decimate and truncate the input audio signal to create a noisy, distorted sound.

### **Decimator**

Controls the resulting bit-resolution. The lower the resolution, the higher the distortion effect.

### **Mode**

Allows you to select one of the four operating modes. In each mode, the effect sounds differently. Modes **I** and **III** are nastier and noisier, while modes **II** and **IV** are more subtle.

### **S&H**

Sets the amount by which the audio samples are decimated. At the highest setting, nearly all of the information describing the original audio signal is eliminated, turning the signal into unrecognizable noise.

## **Delay**

To open the **Delay** section, click the **Delay** button.

### **Time**

Sets the delay time.

### **Duck**

Determines how much the delay signal ducks when an audio signal is present.

### Mix

Sets the level balance between the dry signal and the wet signal.

### FBK

Determines the number of repeats for each delay.

### Mode

If this option is activated, the delay signal is routed back into the distortion unit to create a feedback with distortion.

### NOTE

High **FBK** values and low **Duck** values in combination with activated **Mode** can lead to unwanted noise.

---

## Slider

### Width

Sets the stereo width for the corresponding band.

### Out

Sets the output gain for the corresponding band.

### Pan

Sets the stereo position for the corresponding band.

### Mix

Sets the level balance between the dry signal and the wet signal.

## REvelation

**REvelation** produces a high-quality algorithmic reverb with early reflections and reverb tail.



The early reflections are responsible for the spatial impression in the first milliseconds of the reverb. For emulating different rooms, you can choose between different early reflections patterns and adjust their size. The reverb tail, or late reverberation, offers parameters for



controlling the room size and the reverb time. You can adjust the reverb time individually in 3 frequency bands.

#### **Pre-Delay**

Determines how much time passes before the reverb is applied. This allows you to simulate larger rooms by increasing the time it takes for the first reflections to reach the listener.

#### **Early Reflections**

Here, you select an early reflections pattern. The early reflections pattern contains the most important delays that deliver the key information for the spatial impression of the room.

#### **ER/Tail Mix**

Sets the level balance between the early reflections and the reverb tail. At a setting of 50 %, early reflections and tail have the same volume. Settings below 50 % raise the early reflections and lower the tail, as a result the sound source moves towards the front of the room. Settings above 50 % raise the tail and lower the early reflections, as a result the sound source moves towards the back of the room.

#### **Size**

Adjusts the length of the early reflections pattern. At a setting of 100 %, the pattern is applied with its original length and the room sounds the most natural. At settings below 100 %, the early reflections pattern is compressed and the room is perceived smaller.

#### **Low Cut**

Attenuates the low frequencies of the early reflections. The higher this value, the less low frequencies are present in the early reflections.

#### **High Cut**

Attenuates the high frequencies of the early reflections. The lower this value, the less high frequencies the early reflections will have.

#### **Delay**

Delays the onset of the reverb tail.

#### **Room Size**

Controls the dimensions of the simulated room. At a setting of 100 %, the dimensions correspond to a cathedral or a large concert hall. At a setting of 50 %, the dimensions correspond to a medium-sized room or studio. Settings below 50 % simulate the dimensions of small rooms or a booth.

#### **Main Time**

Controls the overall reverb time of the tail. The higher this value, the longer the reverb tail will decay. At a setting of 100 %, the reverb time is infinitely long. The **Main Time** parameter also represents the mid band of the reverb tail.

#### **High Time**

Controls the reverb time for the high frequencies of the reverb tail. With positive values, the decay time of the high frequencies is longer. With negative values, it is shorter. Frequencies are affected depending on the **High Freq** parameter.

#### **Low Time**

Controls the reverb time for the low frequencies of the reverb tail. For positive values, low frequencies decay longer and vice versa. Frequencies will be affected depending on the **Low Freq** parameter.

### **High Freq**

Sets the cross-over frequency between the mid and the high band of the reverb tail. You can offset the reverb time for frequencies above this value from the main reverb time with the **High Time** parameter.

### **Low Freq**

Sets the cross-over frequency between the low and the mid band of the reverb tail. The reverb time for frequencies below this value can be offset from the main reverb time with the **Low Time** parameter.

### **Shape**

Controls the attack of the reverb tail. At a setting of 0 %, the attack is more immediate, which is a good setting for drums. The higher this value, the less immediate the attack.

### **Density**

Adjusts the echo density of the reverb tail. At a setting of 100 %, single reflections from walls cannot be heard. The lower this value, the more single reflections can be heard.

### **High Cut**

Attenuates the high frequencies of the reverb tail. The lower this value, the less high frequencies the reverb tail will have.

### **Width**

Controls the width of the stereo image. At a setting of 0 %, the output of the reverb is mono, at 100 % it is stereo.

### **Mix**

Sets the level balance between the dry signal and the wet signal. If the effect is used as a send effect, set this parameter to the maximum value, as you can control the dry/effect balance with the send level.

### **Lock Mix Value**

Activate this button (padlock symbol) next to the **Mix** parameter to lock the dry/wet balance while browsing through the available presets.

## **Modulation**

Modulation allows you to enrich the reverb tail through subtle pitch modulations.

### **Modulation Rate**

Specifies the frequency of the pitch modulation.

### **Modulation Depth**

Sets the intensity of the pitch modulation.

### **Modulation Activate**

Activates/Deactivates the chorusing effect.

## **RoomWorks**

**RoomWorks** is a highly adjustable reverb plug-in for creating realistic room ambience and reverb effects in stereo and surround formats. The CPU usage is adjustable to fit the needs of any

system. From short room reflections to cavern-sized reverb, this plug-in delivers high quality reverberation.



## Input Filters

### Low Frequency

Determines the frequency at which the low-shelving filter takes effect. Both the high and low settings filter the input signal prior to reverb processing.

### High Frequency

Determines the frequency at which the high-shelving filter takes effect. Both the high and low settings filter the input signal prior to reverb processing.

### Low Gain

Sets the amount of boost or attenuation for the low-shelving filter.

### High Gain

Sets the amount of boost or attenuation for the high-shelving filter.

## Reverb Character

### Pre-Delay

Determines how much time passes before the reverb is applied. This allows you to simulate larger rooms by increasing the time it takes for the first reflections to reach the listener.

### Size

Alters the delay times of the early reflections to simulate larger or smaller spaces.

### Reverb Time

Allows you to set the reverb time in seconds.

### Diffusion

Affects the character of the reverb tail. Higher values lead to more diffusion and a smoother sound, while lower values lead to a clearer sound.

### Width

Controls the width of the stereo image. At a setting of 0 %, the output of the reverb is mono, at 100 % it is stereo.

### Variation

Clicking this button generates a new version of the same reverb program using altered reflection patterns. This is helpful if some sounds are causing odd ringing or

undesirable results. Creating a new variation often solves these issues. There are 1000 possible variations.

### **Hold**

Activating this button freezes the reverb buffer in an infinite loop. You can create some interesting pad sounds using this feature.

## **Damping**

### **Low Frequency**

Determines the frequency below which low-frequency damping occurs.

### **High Frequency**

Determines the frequency above which high-frequency damping occurs.

### **Low Level**

Affects the decay time of the low frequencies. Normal room reverb decays quicker in the high- and low-frequency range than in the mid-range. Lowering the level percentage causes low frequencies to decay quicker. Values above 100 % cause low frequencies to decay more slowly than the mid-range frequencies.

### **High Level**

Affects the decay time of the high frequencies. Normal room reverb decays quicker in the high- and low-frequency range than in the mid-range. Lowering the level percentage causes high frequencies to decay quicker. Values above 100 % cause high frequencies to decay more slowly than the mid-range frequencies.

## **Envelope**

### **Amount**

Determines how much the envelope attack and release controls affect the reverb itself. Lower values have a more subtle effect while higher values lead to a more drastic sound.

### **Attack**

The envelope settings in **RoomWorks** control how the reverb follows the dynamics of the input signal in a fashion similar to a noise gate or downward expander. Attack determines how long it takes for the reverb to reach full volume after a signal peak (in milliseconds). This is similar to a pre-delay, but the reverb is ramping up instead of starting all at once.

### **Release**

Determines how long after a signal peak the reverb can be heard before being cut off, similar to a release time of a gate.

## **Output**

### **Mix**

Sets the level balance between the dry signal and the wet signal. If **RoomWorks** is used as an insert effect for an FX channel, you most likely want to set this to 100 % or use the **wet only** button.

### **Wet only**

This button deactivates the **Mix** parameter, setting the effect to 100 % wet or affected signal. This button should normally be activated if **RoomWorks** is used as a send effect for an FX channel or a group channel.

### Efficiency

Determines how much processing power is used for **RoomWorks**. The lower the value, the more CPU resources are used, and the higher the quality of the reverb. Interesting effects can be created with very high **Efficiency** settings (>90%).

### Export

Determines if during audio export **RoomWorks** uses the maximum CPU power for the highest quality reverb. During export, you may want to keep a higher efficiency setting to achieve a specific effect. If you want the highest quality reverb during export, make sure this button is activated.

### Output meter

Shows the level of the output signal.

## RoomWorks SE

**RoomWorks SE** is a smaller version of the **RoomWorks** plug-in. **RoomWorks SE** delivers high quality reverberation, but has fewer parameters and is less CPU demanding than the full version.



### Pre-Delay

Determines how much time passes before the reverb is applied. This allows you to simulate larger rooms by increasing the time it takes for the first reflections to reach the listener.

### Reverb Time

Allows you to set the reverb time in seconds.

### Diffusion

Affects the character of the reverb tail. Higher values lead to more diffusion and a smoother sound, while lower values lead to a clearer sound.

### Low Level

Affects the decay time of the low frequencies. Normal room reverb decays quicker in the high- and low-frequency range than in the mid-range. Lowering the level percentage causes low frequencies to decay quicker. Values above 100 % cause low frequencies to decay more slowly than the mid-range frequencies.

### High Level

Affects the decay time of the high frequencies. Normal room reverb decays quicker in the high- and low-frequency range than in the mid-range. Lowering the level percentage causes high frequencies to decay quicker. Values above 100 % cause high frequencies to decay more slowly than the mid-range frequencies.

## Mix

Sets the level balance between the dry signal and the wet signal. When using **RoomWorks SE** inserted in an FX channel, you most likely want to set this to 100 %.

# Squasher

**Squasher** is a multi-band compressor that combines upward and downward compression, allowing you to squash the audio signal. You can set up different parameters for up to three frequency bands and use internal side-chaining to control the amount of compression for each band.



## Main section

This section provides general settings for upward and downward compression for each frequency band.

### Frequency/Compressor display

Displays the frequency spectrum. It allows you to edit the band range, the output level, the upward/downward ratio, and the upward/downward threshold for each band. You can switch the display between a frequency spectrum view and a compressor characteristics view by clicking the corresponding buttons left of the display:



Frequency spectrum



Compressor characteristics

You can edit the output level of a band or the cutoff frequency between two bands by dragging the corresponding handle in the frequency spectrum display.

### Show/Hide Full Frequency Band View

Shows/Hides the frequency spectrum/compressor display.

### Input meter

Shows the level of the overall input signal.

### Input

Sets the overall input level.

### Bands

Sets the number of frequency bands.

### Mix

Adjusts the mix between dry signal and wet signal, preserving the transients of the input signal.

### Parameter Link

Links the parameters of the same type in all bands. This allows you to edit parameter values of all bands in a module simultaneously. Two link modes are available:

- If **Absolute Mode** is activated and you edit a parameter value of one band, the corresponding parameter values of the other bands are set to the same value.
- If **Relative Mode** is activated and you edit a parameter value of one band, the relation of the corresponding parameter values of the other bands remains the same.

### Activate/Deactivate Band

Activates/Deactivates the corresponding frequency band.

### Solo Band

Solos the corresponding frequency band.

### Up Ratio/Down Ratio

Set the amount of upward and downward compression. These parameters allow you to adjust the squashing effect.

### In

Shows the input level for the corresponding frequency band.

### Up Threshold/Down Threshold

The left triangle sets the threshold for upward compression. If the input signal is below this threshold, the upward compressor raises the level according to the **Up Ratio** value.

The right triangle sets the threshold for downward compression. If the input signal is above this threshold, the downward compressor lowers the level according to the **Down Ratio** value.

You can drag the darker area between both handles to adjust **Up Threshold** and **Down Threshold** simultaneously.

### **Output meter**

Shows the level of the overall output signal.

### **Output**

Sets the overall output level.

## **Squash Parameter section**

This section provides additional compression and filter settings for each frequency band.

### **Show/Hide Squash Parameter Section**

Shows/Hides the squash parameter section.

### **Att.**

Sets the compression attack time for both the upward and downward compressor.

### **Rel.**

Sets the compression release time for both the upward and downward compressor.

### **Drive**

Sets the amount of saturation. This parameter adds harmonics to the output signal.

### **Gate**

Sets the threshold for the internal gating effect. Signal levels above this threshold trigger the gate to open. Signal levels below this threshold close the gate.

#### **NOTE**

You can control this parameter via side-chaining.

---

### **Mix**

Adjusts the mix between dry signal and wet signal for the corresponding band.

### **Output**

Sets the output level for the corresponding band.

#### **NOTE**

Alternatively, you can edit this parameter by dragging the corresponding handle in the frequency display.

---

## **Side-Chain section**

This section provides settings for internal side-chaining for each frequency band. It is only available if the parameter section is shown.

### **Show/Hide Side-Chain Section**

Shows/Hides the side-chaining section.

### **Activate/Deactivate Side-Chaining for Band**

Activates/Deactivates side-chaining for the corresponding band.

### **Side-Chain Filter Listen**



Lets you monitor the side-chain signal and the applied filter.

### **Freq**

Sets the frequency of the side-chain filter.



## Q

Sets the Q factor of the side-chain filter.

## Send to

This pop-up menu allows you to send the side-chain signal to the compressor section (**Squasher**) or to the internal gate.

# SuperVision

**SuperVision** is a professional tool suite for monitoring and analyzing your audio. The plug-in comes with several different modules for level, spectral, phase, or waveform analysis. Up to nine module slots allow you to create custom layouts for better overview.

**SuperVision** features two different processing modes: **Maximum Audio Performance** and **Sample-Accurate Display**. You can choose which mode to use for each module independently.



## Toolbar

### Pause Measurement



Pauses/Continues the measurement for the selected module. **Alt/Opt**-click this button to pause/continue all modules at the same time.

#### NOTE


- You can also pause/continue the measurement for the selected module by right-clicking it.
- If a module is paused, you can still adjust the graphical display that holds the last measured values.
- For all modules that show a playback cursor, you can click in the paused display to set the project cursor to this position. This is not possible during recording.

### Hold Current Values on Stop



If this button is activated, the last measured values remain in the display when playback is stopped.

#### Module selector




Allows you to select a module for the selected slot.

#### Open Module Settings



Opens the **Module Settings** window. It provides the settings for the selected module.

#### Channel selector



Allows you to select which channels are displayed. The available channel configurations depend on the channel configuration of the track and on the selected module.

**Mixdown** allows you to display the average value of all channels within the track.

#### NOTE

- The channel selector is only available for configurations with two or more channels.

---

#### Reset Module Values



Resets the measured values of the selected module. **Alt/Opt**-click to reset all modules at the same time.

#### NOTE

You can also reset the measured values of a module by **Ctrl/Cmd**-clicking it.

---

#### Reset Module Values on Start



If this button is activated, all values are automatically reset when you start playback.

#### Split Horizontally



Splits the selected module slot horizontally.

#### NOTE

This button is not available if a module is maximized.

---

#### Split Vertically



Splits the selected module slot vertically.

#### NOTE

This button is not available if a module is maximized.

---

### Module Slot Controls

Each module slot shows the following controls in the top right corner if you move the mouse over it:

### Remove module slot



Removes the module slot from the current plug-in layout.

### Split horizontally



Splits the module slot horizontally.

### Split vertically



Splits the module slot vertically.

You can maximize a module by double-clicking it. To downsize it, double-click it again or click the standard view button

If your layout shows more than one module, you can change the focus by clicking a module or pressing **Tab**.

In some modules, for example, **Level**, **Loudness**, or **Time**, you can click **Ctrl/Cmd-S** to copy parameter values as text from the selected module to the clipboard for further use in other applications.

You can show the current frames per second (fps) for all modules by clicking **Alt/Opt-F**.

#### RELATED LINKS

[Module Settings Window](#) on page 83

[Signal Modules](#) on page 84

[Spectral Domain Modules](#) on page 94

[Phase Modules](#) on page 100

[Spatial Domain Modules](#) on page 103

[Waveform Modules](#) on page 105

[Other Modules](#) on page 108

## Module Settings Window

In the **Module Settings** window, you can make individual settings for the selected module.

- To open the **Module Settings** window, click **Open Module Settings**

The settings on the **Module Settings** window toolbar are available for all modules:

### Reset Settings



Resets all parameter settings to the default values of the selected module.

### Maximum Audio Performance/Sample-Accurate Display



Sets the processing mode for the selected module.

If this button is activated, **Maximum Audio Performance** is selected. In this mode, the plug-in has no impact on the audio performance, but the analysis might not be sample-accurate.

If this button is deactivated, **Sample-Accurate Display** is selected. In this mode, no audio sample gets lost for analysis, but the audio performance might be slightly reduced.

NOTE

**Sample-Accurate Display** is not available for all modules.

---

### Enable Warnings



If this button is activated, a red border around the affected module indicates that the displayed analysis result might not be completely sample-accurate.

NOTE

This setting is only available in **Maximum Audio Performance** mode.

---

### Force Horizontal Display



If this button is activated, the module is always displayed horizontally when you resize it.

NOTE

This setting is not available for all modules.

---

### Force Vertical Display



If this button is activated, the module is always displayed vertically when you resize it.

NOTE

This setting is not available for all modules.

---

For the specific settings of a module, see the corresponding module description.

By default, only the top row of controls is displayed. **Advanced** shows/hides all settings for a module.

#### RELATED LINKS

[Signal Modules](#) on page 84

[Spectral Domain Modules](#) on page 94

[Phase Modules](#) on page 100

[Spatial Domain Modules](#) on page 103

[Waveform Modules](#) on page 105

[Other Modules](#) on page 108


## Signal Modules

The modules in this category allow you to visualize the level of the audio signal.

The following modules and module-specific settings are available:

### Level

This module shows the level of your audio. It provides a multi-channel level meter and a maximum level value display.



The following module-specific settings are available in the **Module Settings** window:

### Scale

Allows you to select a scale according to different broadcast standards (**Internal**, **Digital**, **DIN**, **EBU**, **British**, **Nordic**, **K-20**, **K-14**, **K-12**, **+3 dB Digital**, **+6 dB Digital**, or **+12 dB Digital**).

### Peak Hold

Specifies for how long the peak levels are held in the display.

### Peak Fallback

Sets the speed of release for the level meters and peak indicators.

#### NOTE

- Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter.
- If this control is turned all the way to the left, the peak indicators are disabled.

### Threshold

Sets a threshold level below which the display is masked.

#### NOTE

Alternatively, you can move the mouse pointer over the selected module and use the mouse wheel to adjust this parameter.

### Offset

Sets the offset between measured and displayed value in dB.

This parameter is only available for the **DIN**, **EBU**, **British**, and **Nordic** scale.

### Clipping

Sets the clipping value for the **Internal** scale.

### Minimum

Sets the minimum value for the **Internal** scale.

### Maximum

Sets the maximum value for the **Internal** scale.

### Color

Sets the color of the meters. You can choose between the **Scale** color and the **Track** color.

### RMS AES17

Shows the level in accordance with AES17 (RMS +3 dB).

### RMS Resolution

Sets the RMS resolution for the level display in milliseconds.


### Max. Value

Sets the measurement mode for the maximum level value display. The following modes are available:

- **True Peak** shows estimated real peak value for each channel.
- **Peak Max.** shows maximum sample value for each channel.
- **RMS Max.** shows the maximum RMS value for each channel.
- **RMS Max. + True Peak** shows the highest maximum RMS and the highest estimated real peak value of all channels.
- **RMS Max. + Peak Max.** shows the highest maximum RMS and the highest maximum sample value of all channels.

## VU

This module shows the level of your audio on a classic VU meter. In addition to the VU meter needle and the LED peak indicator, it provides a peak level indicator needle and a numeric maximum level value display.



The following module-specific settings are available in the **Module Settings** window:

### Scale

Allows you to select a scale according to different broadcast standards (**Internal, Digital, DIN, EBU, British, Nordic, K-20, K-14, K-12, +3 dB Digital, +6 dB Digital, +12 dB Digital, VU dB, and VU dBFS**).

### Peak Hold

Specifies for how long the peak levels are held in the display.

### Peak Fallback

Sets the speed of release for the level meters and peak indicators.

#### NOTE

- Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter.
- If this control is turned all the way to the left, the peak indicators are disabled.

### Meter Mode

Sets the behavior of the needle.

- **VU** mode imitates the physical behavior of an analog VU meter that shows the current peak value.
- **Peak** mode shows the current peak value.
- **RMS** mode shows the current RMS value.

### Offset

Sets the offset between measured and displayed value in dB.

This parameter is only available for the **DIN**, **EBU**, **British**, and **Nordic** scale.

### Clipping

Sets the clipping value for the **Internal** scale.

### Minimum

Sets the minimum value for the **Internal** scale.

### Maximum

Sets the maximum value for the **Internal** scale.

### Color

Sets the color of the meters. You can choose between the **Track** color and a **Dark** or **Light** scheme.

### RMS AES17

Shows the level in accordance with AES17 (RMS + 3 dB).

### RMS Resolution

Sets the RMS resolution for the level display in milliseconds.


### Max. Value

Sets the measurement mode for the maximum level value display. The following modes are available:

- **True Peak** shows the estimated real peak value for each channel.
- **Peak Max.** shows the maximum sample value for each channel.
- **RMS Max.** shows the maximum RMS value for each channel.
- **RMS Max. + True Peak** shows the highest maximum RMS and the highest estimated real peak value of all channels.
- **RMS Max. + Peak Max.** shows the highest maximum RMS and the highest maximum sample value of all channels.

## Level Histogram

This module shows a histogram for the peak or RMS value of the input level.



The following module-specific settings are available in the **Module Settings** window:

### Scale

Allows you to select a scale according to different broadcast standards (**Internal**, **Digital**, **DIN**, **EBU**, **British**, **Nordic**, **K-20**, **K-14**, **K-12**, **+3 dB Digital**, **+6 dB Digital**, or **+12 dB Digital**).

### Meter Mode

Sets the displayed level value.

- **Peak** mode shows a histogram of the peak value.
- **RMS** mode shows a histogram of the RMS value.

### Peak Fallback

Sets the speed of release for the level meters and peak indicators.

#### NOTE

- If you change this parameter during playback, you must click **Reset Module Values** to update the display.
  - Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter.
  - If this control is turned all the way to the left, the peak indicators are disabled.
- 

### Offset

Sets the offset between measured and displayed value in dB.

This parameter is only available for the **DIN**, **EBU**, **British**, and **Nordic** scale.

### Clipping

Sets the clipping value for the **Internal** scale.

### Minimum

Sets the minimum value for the **Internal** scale.

### Maximum

Sets the maximum value for the **Internal** scale.

### RMS AES17

Shows the level in accordance with AES17 (RMS +3 dB).

### RMS Resolution

Sets the RMS resolution for the level display in milliseconds.

### Smooth

Smooths the display of the level curve.

#### NOTE

Alternatively, you can move the mouse pointer over the selected module and use the mouse wheel to adjust this parameter.

---

## Measurement Modules

The modules in this category allow you to measure the loudness and intelligibility of the audio signal.


The following modules and module-specific settings are available:

### Leq(m)/Leq(a)

These modules show the average volume over time, using a filter that emphasizes the mid and upper range frequencies. The Leq(m) measurement uses an M-weighting, according to the Trailer Audio Standards Association (TASA). It is mainly used to ensure that a film trailer



respects the volume limits for trailers in movie theaters. The similar Leq(a) measurement uses an A-weighting and is used to verify the conformity of the sound for broadcasting.




The following module-specific setting is available in the **Module Settings** window:

#### Ref. Level

Sets the reference level above which the Leq(m)/Leq(a) value turns red, indicating that the volume limit is exceeded.

#### Loudness

This module shows the loudness of your audio in LU (Loudness Units) or LUFS (Loudness Units referenced to Full Scale) according to EBU R 128.



#### TP (True Peak)

Shows the maximum true peak level in dB.

#### I (Integrated)

Shows the integrated loudness value. This is the average loudness value that is measured over the whole audio range in LU or LUFS.

#### S (Short-Term)

Shows the short-term loudness value that is measured every second on an audio block of 3 seconds in LU or LUFS. This gives information about the loudest audio passages.

#### M Max. (Momentary Max.)

Shows the maximum value of all momentary loudness values that are measured every 100 ms in an audio range of 400 ms in LU or LUFS.

### **R (Range)**

Shows the loudness range (LRA) that is measured over the whole audio range in LU.

The loudness range reports the ratio between the loudest and the quietest non-silent sections. The audio is divided into small blocks. There is one audio block every second and each block lasts 3 seconds, so that the analyzed blocks overlap. The top 10 % of the quiet blocks and the top 5 % of the loud blocks are excluded from the final analysis. The calculated loudness range is the ratio between the loudest and quietest remaining audio blocks. This measurement helps you to decide how much compression or expansion must be applied to the audio.

An asterisk (\*) after a loudness range value indicates that less than 1 minute of audio was analyzed.

**Min.** shows the minimum loudness range value in LU. **Max.** shows the maximum loudness range value in LU.

#### NOTE

EBU R 128 does not recommend loudness range measurement for audio shorter than 1 minute due to too few data points.

---

### **PLR (Peak-to-Loudness)**

Shows the peak-to-loudness ratio (PLR), also referred to as the crest factor, which is the difference between the maximum true peak level value and the integrated loudness value.

### **Time**

Shows the overall duration of the loudness measurement.

The following module-specific settings are available in the **Module Settings** window:

### **Unit**

Allows you to switch the meter scale between LUFs (absolute values) and LU (relative values).

### **Scale**

Allows you to switch the meter between the EBU +9 scale and the EBU +18 scale.

### **Ref. Integrated**

Sets a reference value for the integrated loudness. If higher values are detected, the loudness meter indicates clipping.

### **Tol. Integrated**

Sets a tolerance value for the integrated loudness.

### **Ref. True Peak**

Sets a reference value for the true peak level. If higher values are detected, the loudness meter indicates clipping.

### **Tol. True Peak**

Sets a tolerance value for the true peak level.

### **Ref. Short-Term**

Sets a reference value for the short-term loudness. If higher values are detected, the loudness meter indicates clipping.

### **Tol. Short-Term**

Sets a tolerance value for the short-term loudness.

### Ref. Momentary

Sets a reference value for the maximum momentary loudness. If higher values are detected, the loudness meter indicates clipping.

### Tol. Momentary

Sets a tolerance value for the maximum momentary loudness.

### Ref. Range


Sets a reference value for the loudness range. If higher values are detected, the loudness meter indicates clipping.

### Tol. Range

Sets a tolerance value for the loudness range.

## Loudness (Netflix)

This module provides a dialogue-gated loudness measurement that uses the Dolby Dialogue Intelligence algorithm according to ITU-R BS.1770 and shows the loudness of your audio in LU (Loudness Units) or LUFS (Loudness Units referenced to Full Scale). The **Dialogue** value allows you to assess the percentage of speech-based sequences within the audio.



### NOTE

When using the **Loudness (Netflix)** measurement, the Dolby Dialogue Intelligence algorithm adds a latency of 2.048 seconds compared to the standard **Loudness** measurement.

---

### TP (True Peak)

Shows the maximum true peak level in dB.

### I (Integrated)

Shows the integrated loudness value. This is the average loudness value that is measured over the whole audio range in LU or LUFS.

### S (Short-Term)

Shows the short-term loudness value that is measured every second on an audio block of 3 seconds in LU or LUFS. This gives information about the loudest audio passages.

### M Max. (Momentary Max.)

Shows the maximum value of all momentary loudness values that are measured every 100 ms in an audio range of 400 ms in LU or LUFS.

### R (Range)

Shows the loudness range (LRA) that is measured over the whole audio range in LU.

The loudness range reports the ratio between the loudest and the quietest non-silent sections. The audio is divided into small blocks. There is one audio block every second and each block lasts 3 seconds, so that the analyzed blocks overlap. The top 10 % of the quiet blocks and the top 5 % of the loud blocks are excluded from the final analysis. The calculated loudness range is the ratio between the loudest and quietest remaining

audio blocks. This measurement helps you to decide how much compression or expansion must be applied to the audio.

An asterisk (\*) after a loudness range value indicates that less than 1 minute of audio was analyzed.

**Min.** shows the minimum loudness range value in LU. **Max.** shows the maximum loudness range value in LU.

**NOTE**

EBU R 128 does not recommend loudness range measurement for audio shorter than 1 minute due to too few data points.

---

**Dlg. (Dialogue)**

Shows the overall percentage of speech that is detected in the measured audio. The speaker icon indicates that speech is detected at the current cursor position during playback.

**NOTE**

If at least 15 % of speech is detected, a dialogue-gated measurement according to ITU-R BS.1770-1 is used for visualization. If less speech is detected, a program-gated measurement according to ITU-R BS.1770-3 is used.

---

**Time**

Shows the overall duration of the loudness measurement.

The following module-specific settings are available in the **Module Settings** window:

**Unit**

Allows you to switch the meter scale between LUFs (absolute values) and LU (relative values).

**Scale**

Allows you to switch the meter between the EBU +9 scale and the EBU +18 scale.

**Ref. Integrated**

Sets a reference value for the integrated loudness. If higher values are detected, the loudness meter indicates clipping.

**Tol. Integrated**

Sets a tolerance value for the integrated loudness.

**Ref. True Peak**

Sets a reference value for the true peak level. If higher values are detected, the loudness meter indicates clipping.

**Tol. True Peak**

Sets a tolerance value for the true peak level.

**Ref. Short-Term**

Sets a reference value for the short-term loudness. If higher values are detected, the loudness meter indicates clipping.

**Tol. Short-Term**

Sets a tolerance value for the short-term loudness.

### Ref. Momentary

Sets a reference value for the maximum momentary loudness. If higher values are detected, the loudness meter indicates clipping.

### Tol. Momentary

Sets a tolerance value for the maximum momentary loudness.

### Ref. Range


Sets a reference value for the loudness range. If higher values are detected, the loudness meter indicates clipping.

### Tol. Range

Sets a tolerance value for the loudness range.

## Loudness Histogram

This module shows a histogram for the loudness or the loudness ratio value.



The following module-specific settings are available in the **Module Settings** window:

### Unit

Allows you to switch the meter scale between LUFS (absolute values) and LU (relative values).

### Scale

Allows you to switch the meter between the EBU +9 scale and the EBU +18 scale.

### Meter Mode

Sets the displayed loudness or loudness ratio value.

- **Momentary** mode shows a histogram of the maximum value of all momentary loudness values that are measured every 100 ms in an audio range of 400 ms.
- **Short-Term** shows a histogram of the short-term loudness value that is measured every second on an audio block of 3 seconds.
- **Integrated** shows a histogram of the integrated loudness value.
- **PLR** shows a histogram of the peak-to-loudness ratio, also referred to as the crest factor, which is the difference between the maximum true peak level value and integrated loudness value.
- **PSR** shows a histogram of the peak-to-short-term-loudness ratio according to AES Convention e-Brief 373.

### Smooth

Smooths the display of the loudness curve.


**NOTE**

Alternatively, you can move the mouse pointer over the selected module and use the mouse wheel to adjust this parameter.

---

## Loudness Ratio

This module shows the peak-to-loudness ratio (PLR) and the peak-to-short-term-loudness ratio (PSR) values according to AES specifications.



### PSR

Shows the peak-to-short-term-loudness ratio according to AES Convention e-Brief 373. The darker area of the meter indicates the minimum PSR value.

### PLR

Shows the peak-to-loudness ratio, also referred to as the crest factor, which is the difference between the maximum true peak level value and integrated loudness value. The current PLR value is displayed numerically and also indicated by a thin bar on the meter.

The following module-specific setting is available in the **Module Settings** window:

### Ref. Level

Sets the reference level above which the PSR and PLR display turns red.


## Spectral Domain Modules

The modules in this category allow you to visualize spectral information about the audio signal.

The following modules and module-specific settings are available:

### Spectrum Curve

This module uses FFT (Fast Fourier Transform) techniques to show a frequency graph, providing a precise and detailed real-time frequency analysis.



The display shows the frequency spectrum as a linear graph. If you move the mouse pointer over the display, a peak curve is shown in orange. Move the mouse pointer over the curves to show the local maximum values in Hz. Press **Ctrl/Cmd** to show the maximum values in dB or press **Shift** to show their pitch.

The following module-specific settings are available in the **Module Settings** window:

#### Time Smooth

Smooths the temporal display of the spectrum curve.

##### NOTE

Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter.

---

#### Peak Fallback

Sets the speed of release for the spectrum curve and the peak curve.

##### NOTE

- Alternatively, you can move the mouse pointer over the selected module, hold **Ctrl/Cmd**, and use the mouse wheel to adjust this parameter.
  - If this control is turned all the way to the left, the peak curve is disabled.
- 

#### Freq. Smooth

Smooths the frequency display of the spectrum curve.

##### NOTE

Alternatively, you can move the mouse pointer over the selected module and use the mouse wheel to adjust this parameter.

---

#### FFT Window

Sets the block size of the window that is used for the analysis. If **Multi** is selected, 3 different block sizes are used at the same time.

#### Minimum

Sets the minimum value of the scale.

#### Maximum


Sets the maximum value of the scale.

#### Slope

Adds a slope to the frequency spectrum.

## Spectrum Bar

This module shows a graphical representation of the frequency spectrum, analyzed into separate frequency bands, represented as vertical bars.



Move the mouse pointer over a bar to show the frequency range in Hz. Press **Ctrl/Cmd** to show the current value in dB or press **Shift** to show its pitch range.

The following module-specific settings are available in the **Module Settings** window:

### Time Smooth

Smooths the temporal display of the spectrum curve.

#### NOTE

Alternatively, you can move the mouse pointer over the selected module, hold **⌘**, and use the mouse wheel to adjust this parameter.

---

### Peak Fallback

Sets the speed of release for the level meters and peak indicators.

#### NOTE

- Alternatively, you can move the mouse pointer over the selected module, hold **⌘**, and use the mouse wheel to adjust this parameter.
  - If this control is turned all the way to the left, the peak indicators are disabled.
- 

### Threshold

Sets a threshold level below which the display is masked.

#### NOTE

Alternatively, you can move the mouse pointer over the selected module and use the mouse wheel to adjust this parameter.

---

### Bands/Oct.

Sets the number of bands per octave.

### Minimum

Sets the minimum value of the scale.

### Maximum

Sets the maximum value of the scale.


### Slope

Adds a slope to the frequency spectrum.



## Spectrum Intensity

This module represents the frequency magnitude of the audio. The more intensely a bar is colored, the higher the magnitude at this frequency.



The following module-specific settings are available in the **Module Settings** window:

### Time Smooth

Smooths the temporal display of the spectrum curve.

#### NOTE

Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter.

### FFT Window

Sets the block size of the window that is used for the analysis. If **Multi** is selected, 3 different block sizes are used at the same time.

### Color

Allows you to choose a color scheme.

### Minimum

Sets the minimum value of the scale.

### Maximum


Sets the maximum value of the scale.

### Slope

Adds a slope to the frequency spectrum.

## Spectrum Keyboard

This module represents the frequency magnitude of the audio mapped to the keys of a piano keyboard. The more intensely a key is colored, the higher the magnitude at its frequency.



The following module-specific settings are available in the **Module Settings** window:

### Time Smooth

Smooths the temporal display of the spectrum curve.

#### NOTE

Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter.

---

### Color

Allows you to choose a color scheme.

### Minimum

Sets the minimum value of the scale.

### Maximum


Sets the maximum value of the scale.

### Slope

Adds a slope to the frequency spectrum.

## Spectrogram

This module shows the last seconds of the audio stream. This allows you to detect disturbances in the spectrogram and to monitor the noise level and frequencies, for example.



#### NOTE

This module runs in **Maximum Audio Performance** mode.

---

The following module-specific settings are available in the **Module Settings** window:

### FFT Window

Sets the block size of the window that is used for the analysis. This allows you to adjust the trade-off between temporal resolution and frequency resolution. If you specify a higher value, more frequencies are analyzed but they are located less accurately in the time domain.

### Duration

Sets the duration of the audio stream that is displayed.

#### NOTE

Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter.

---

### Color

Allows you to choose a color scheme.

### Minimum

Sets the minimum value of the scale.

### Maximum

Sets the maximum value of the scale.


#### NOTE

Alternatively, you can move the mouse pointer over the selected module and use the mouse wheel to adjust the **Minimum** and **Maximum** parameters simultaneously.

---

## Chromagram

This module displays a chromagram of your audio.



#### NOTE

This module runs in **Maximum Audio Performance** mode.

---

The following module-specific settings are available in the **Module Settings** window:

### Duration

Sets the duration of the audio stream that is displayed.

#### NOTE

Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter.

---

### Color

Allows you to choose a color scheme.

### Minimum

Sets the minimum value of the scale.

### Maximum

Sets the maximum value of the scale.

#### NOTE

Alternatively, you can move the mouse pointer over the selected module and use the mouse wheel to adjust the **Minimum** and **Maximum** parameters simultaneously.

---


## Phase Modules

The modules in this category allow you to visualize the phase or directional relationship between the channels of the audio signal.

The following modules and module-specific settings are available:

### Phasescope

This module uses a vectorscope display to show the phase and amplitude relationship between the left and right stereo channels. This provides you with directional information about a stereo audio signal.



Hold **Shift** and move the mouse pointer over the display to measure the angle.

The following module-specific settings are available in the **Module Settings** window:

#### Zoom

Allows you to zoom in the graphical display.

##### NOTE

Alternatively, you can move the mouse pointer over the selected module and use the mouse wheel to adjust this parameter.

---

#### Auto Zoom

If this button is activated, the zoom factor is adapted automatically.

#### Mode

Sets the display mode. The following modes are available: **Lines**, **Dots**, **Envelope**.

#### Peak Fallback

Sets the speed of release for the peak envelope in **Envelope** mode.

##### NOTE

If this control is turned all the way to the left, the peak envelope is disabled.

---

#### Scale

Activates/Deactivates the axis labeling.


##### NOTE

This option is only available if **Auto Zoom** is deactivated.

---

## Panorama

This module uses a polar coordinate display to show the phase and amplitude relationship between the left and right stereo channels. This provides you with directional information about a stereo audio signal.



The following module-specific settings are available in the **Module Settings** window:

### Zoom

Allows you to zoom in the graphical display.

#### NOTE

Alternatively, you can move the mouse pointer over the selected module and use the mouse wheel to adjust this parameter.

---

### Auto Zoom

If this button is activated, the zoom factor is adapted automatically.

### Mode

Sets the display mode. The following modes are available: **Lines**, **Dots**, **Envelope**.

### Peak Fallback

Sets the speed of release for the peak envelope in **Envelope** mode.

#### NOTE

If this control is turned all the way to the left, the peak envelope is disabled.

---

### Scale

Activates/Deactivates the axis labeling.


#### NOTE

This option is only available if **Auto Zoom** is deactivated.

---

## Multipanorama

This module provides you with frequency-dependent directional information about a stereo audio signal.



The following module-specific settings are available in the **Module Settings** window:

#### **Time Smooth**

Sets the time for which an energy impulse is displayed.

#### **Bands/Oct.**


Sets the number of bands per octave.

#### **Color**

Allows you to choose a color scheme.

### **Correlation**

This module visualizes the phase-correlation between the left and right channel. This allows you, for example, to check the mono compatibility of a stereo recording.



The following module-specific setting is available in the **Module Settings** window:

#### **Time Smooth**


Smooths the temporal display of the correlation.

#### **NOTE**

Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter

### **Multicorrelation**

This module visualizes the phase-correlation between the left and right channel for different frequency bands.



Move the mouse pointer over a bar to display its frequency range in Hz. Hold **Ctrl/Cmd** to display its current value. Hold **Shift** to display its pitch range.

The following module-specific settings are available in the **Module Settings** window:

#### Time Smooth

Smooths the temporal display of the correlation.

##### NOTE

Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter

---

#### Bands/Oct.

Sets the number of bands per octave.

#### Balance

This module visualizes the balance between the left and right channel.



The following module-specific setting is available in the **Module Settings** window:

#### Time Smooth

Smooths the temporal display of the correlation.

##### NOTE

Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter

---


## Spatial Domain Modules

The modules in this category allow you to visualize the spatial dimension of the audio signal.

The following modules and module-specific settings are available:

## Surround

This module visualizes the level and correlation of the different speakers in a surround speaker setup.



If all channels have the same level, a perfect circle is shown in the center of the display.

### NOTE

This module is only available for channel-based surround configurations. Speaker configurations with top speakers and Ambisonics channels are not supported.

---

The following module-specific settings are available in the **Module Settings** window:

### Zoom

Allows you to zoom in the graphical display.

### NOTE

Alternatively, you can move the mouse pointer over the selected module and use the mouse wheel to adjust this parameter.

---

### Peak Fallback

Sets the speed of release for the peak envelope.

### NOTE

- Alternatively, you can move the mouse pointer over the selected module, hold **Ctrl/Cmd**, and use the mouse wheel to adjust this parameter.
  - If this control is turned all the way to the left, the peak envelope is disabled.
- 


### Scale

Activates/Deactivates the axis labeling for the correlation display.

## Ambisonics

This module allows you to visualize the energy distribution of an Ambisonics signal.





A plane representation of the spherical Ambisonics sound field shows a grid of hexagons. The color of a hexagon indicates the RMS level at this position. A filter allows you to smooth the visualization.

#### NOTE

This module is only available for Ambisonics channel configurations.

The following module-specific settings are available in the **Module Settings** window:

#### Attack

Sets the attack time of the smoothing filter.

#### Release

Sets the release time of the smoothing filter.

#### Minimum

Sets the minimum value of the signal intensity scale.

#### Maximum

Sets the maximum value of the signal intensity scale.

#### Threshold

Sets the minimum signal level that is displayed. This value is indicated by the lower triangle in the color legend on the right. If you change this value, the **Fade Range** value is adjusted accordingly.

#### Fade Range

Sets the level at which a hexagon is displayed fully opaque. This value is indicated by the upper triangle in the color legend on the right.

#### Color

Allows you to choose a color scheme.

#### Resolution

Sets the resolution of the grid.


## Waveform Modules

The modules in this category allow you to visualize the waveform of the audio signal.

The following modules and module-specific settings are available:

## Oscilloscope

This module shows a highly magnified view of the waveform.



The following module-specific settings are available in the **Module Settings** window:

### Zoom

Allows you to zoom in the graphical display by adjusting the amplitude.

#### NOTE

Alternatively, you can move the mouse pointer over the selected module, hold **Alt/Opt**, and use the mouse wheel to adjust this parameter.

---

### Frequency

Allows you to zoom in the graphical display by adjusting the frequency.

#### NOTE

Alternatively, you can move the mouse pointer over the selected module, hold **Ctrl/Cmd**, and use the mouse wheel to adjust this parameter.

---

### Trigger

Sets the channel that is used to synchronize the audio signal.

#### NOTE

Alternatively, you can click the waveform of the corresponding channel.

---

### Scale

Activates/Deactivates the axis labeling.

#### NOTE

This option is only available if **Auto Zoom** is deactivated.


---

### Phase

Allows you to shift the zero-crossing position.

## Wavescope

This module displays the real-time waveform of the audio signal.



Move the mouse pointer over a waveform position to display the corresponding project time.

The following module-specific settings are available in the **Module Settings** window:

#### **Zoom**

Allows you to zoom in the graphical display.

NOTE

Alternatively, you can move the mouse pointer over the selected module and use the mouse wheel to adjust this parameter.

---

#### **Duration**

Sets the duration of the audio stream that is displayed.

NOTE

Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter.

---

#### **Tempo Sync**

If this button is activated, you can set **Duration** in beats.

NOTE

The equivalent duration is limited to a minimum of 0.5 s and a maximum of 30 s.

---

#### **Scale**

Activates/Deactivates the axis labeling.

NOTE

This option is only available if **Auto Zoom** is deactivated.


---

#### **Station. Cursor**

If this button is activated, the waveform moves continuously under the stationary cursor. If this button is deactivated, the waveform is refreshed when the cursor moves over it.

#### **Wavecircle**

This module displays the real-time waveform of the audio signal as a circle.



Move the mouse pointer over a waveform position to display the corresponding project time.

The following module-specific settings are available in the **Module Settings** window:

#### **Zoom**

Allows you to zoom in the graphical display.

##### **NOTE**

Alternatively, you can move the mouse pointer over the selected module and use the mouse wheel to adjust this parameter.

---

#### **Duration**

Sets the duration of the audio stream that is displayed.

##### **NOTE**

Alternatively, you can move the mouse pointer over the selected module, hold **Alt**, and use the mouse wheel to adjust this parameter.

---

#### **Tempo Sync**

If this button is activated, you can set **Duration** in beats.

##### **NOTE**

The equivalent duration is limited to a minimum of 0.5 s and a maximum of 30 s.

---

#### **Reverse**

Changes the rotation direction.

#### **Station. Cursor**

If this button is activated, the waveform moves continuously under the stationary cursor. If this button is deactivated, the waveform is refreshed when the cursor moves over it.

## **Other Modules**

This category provides a time display.

### **Time**

This module shows the current time position of the project cursor.



**NOTE**

If the project cursor is located outside the locator range, the color of the time display changes.

---

The following module-specific setting is available in the **Module Settings** window:

**Mode**

Allows you to select one of the following display modes: **Time**, **Sample**, **Beats**, or **Timecode**.

## StereoDelay

**StereoDelay** has two independent delay lines with freely specified delay time settings.

**NOTE**

This plug-in works only on stereo tracks.

---



**Feedback**

Set the number of repeats for each delay.

**Delay**

Sets the delay time in milliseconds.

**Mix**

Sets the level balance between the dry signal and the wet signal. If the effect is used as a send effect, set this parameter to the maximum value, as you can control the dry/effect balance with the send level.

### Lo Filter

Affects the feedback loop of the effect signal and allows you to roll off low frequencies. The button below the knob activates/deactivates the filter.

### Pan

Sets the stereo position.

### Hi Filter

Affects the feedback loop of the effect signal and allows you to roll off high frequencies. The button below the knob activates/deactivates the filter.

## StereoEnhancer

**StereoEnhancer** expands the stereo width of (stereo) audio material. It cannot be used with mono files.

### NOTE

This plug-in works only on stereo tracks.

---



### Delay

Increases the amount of differences between the left and right channels to further increase the stereo effect.

### Width

Controls the width or depth of the stereo enhancement. Turn clockwise to increase the enhancement.

### Mono


Switches the output to mono, to check for possible unwanted coloring of the sound which sometimes can occur when enhancing the stereo image.

### Color

Generates additional differences between the channels to increase the stereo enhancement.

## Stereo Tools

**Stereo Tools** allows you to pan or position both the left and right channels independently of one another. You can use it for stereo files that you do not want to convert to mono or for fixing a problem with the stereo file, for example.



### Invert Left Phase/Invert Right Phase

Inverts the polarity of an audio channel. You can use it for removing the center information or for fixing a channel that has been inverted, for example.

### Swap Stereo Channels

Swaps the left and right channels.

### Transform

Determines the conversion method:

- **Nothing:** No conversion of the signal.
- **Left/Right -> Mid/Side:** Converts a stereo signal into a mid/side signal.
- **Mid/Side -> Left/Right:** Converts a mid/side signal into a stereo signal.

### Left/Mid Gain (dB)

Sets the gain of the left stereo signal or the mid signal of the M/S signal.

### Right/Side Gain (dB)

Sets the gain of the right stereo signal or of the side signals of the M/S signal.

### Left/Mid Panning (%)

Pans the left stereo signal or the mid signal of the M/S signal.

### Right/Side Panning (%)

Pans the right stereo signal or the side signals of the M/S signal.

## StudioChorus

**StudioChorus** is a two-stage chorus effect that adds short delays to the signal and modulates the pitch of the delayed signals to produce a doubling effect. The two separate stages of chorus modulation are independent and are processed serially (cascaded).



### Delay

Affects the frequency range of the modulation sweep by adjusting the initial delay time.

### Width

Sets the depth of the chorus effect. Higher settings produce a more pronounced effect.

### Spatial

Sets the stereo width of the effect. Turn clockwise for a wider stereo effect.

### Mix

Sets the level balance between the dry signal and the wet signal. If the effect is used as a send effect, set this parameter to the maximum value, as you can control the dry/effect balance with the send level.

### Rate

Sets the sweep rate.

### Waveform Shape

Allows you to select the modulation waveform, altering the character of the chorus sweep. A sine and a triangle waveform are available.


### Lo Filter/Hi Filter

Allow you to roll off low and high frequencies of the effect signal.



## StudioEQ

**Studio EQ** is a high-quality 4-band parametric stereo equalizer. All four bands can act as fully parametric peak filters. In addition, the low and high bands can act as either shelving filters (three types) or as cut filters (low-pass/high-pass).



### Main Layout

#### Reset

**Alt/Opt**-click this button to reset all parameter values.

#### Show Input/Output Spectrum

Shows the spectrum before and after filtering.


#### Output

Adjusts the overall output level.

#### Auto Gain

If this button is activated, the gain is automatically adjusted, keeping the output level nearly constant regardless of the EQ settings.

### Band Settings



#### Activate/Deactivate Band

Activates/Deactivates the corresponding band.

#### NOTE

- If a band is deactivated, you can still modify its parameters.

### Freq

Sets the frequency of the corresponding band. You can set the frequency either in Hz or as a note value. If you enter a note value, the frequency is automatically changed to Hz. For example, a note value of A3 sets the frequency to 440 Hz. When you enter a note value, you can also enter a cent offset. For example, enter A5 -23 or C4 +49.

#### NOTE

- You can adjust the **Freq** parameter of a band in the graphical editor by clicking the corresponding handle and moving the mouse left and right.
  - Ensure that you enter a space between the note and the cent offset. Only in this case, the cent offsets are taken into account.
- 

### Inv

Inverts the gain value of the filter. Use this button to filter out unwanted noise. When looking for the frequency to omit, it sometimes helps to boost it in the first place (set the filter to positive gain). After you have found the frequency of the noise, you can use the **Inv** button to cancel it out.

### Q

For **Peak** filters, this parameter controls the width of the band. For **Shelf** filters, it adds a drop or a boost, depending on the gain setting of the band. For **Cut** filters, it adds a resonance.

#### NOTE

- You can adjust the **Q** parameter of a band in the graphical editor by clicking the corresponding handle and moving the mouse up and down. Alternatively, you can point on the handle and turn the mouse wheel.
- 

### Gain

Sets the amount of attenuation/boost for the corresponding band.

#### NOTE

- You can adjust the **Gain** parameter of a band in the graphical editor by clicking the corresponding handle and moving the mouse up and down.
  - This parameter is not available for **Cut** filters.
- 


### Filter type

For the low and high band, you can choose between three types of shelving filters, a peak filter (band-pass), and a cut filter (low-pass/high-pass). If **Cut** mode is selected, the **Gain** parameter is fixed.

- **Shelf I** adds resonance in the opposite gain direction slightly above the set frequency.
- **Shelf II** adds resonance in the gain direction at the set frequency.
- **Shelf III** is a combination of **Shelf I** and **II**.

## TestGenerator

This utility plug-in allows you to generate an audio signal, which can be recorded as an audio file.



The resulting file can then be used for a number of purposes:

- Testing the specifications of audio equipment
- Measurements of various kinds, such as calibrating tape recorders
- Testing signal processing methods
- Educational purposes

The **TestGenerator** is based on a waveform generator which can generate a number of basic waveforms such as sine and saw as well as various types of noise. Furthermore, you can set the frequency and amplitude of the generated signal. As soon as you add the **TestGenerator** as an effect on an audio track and activate it, a signal is generated. You can then activate recording as usual to record an audio file according to the signal specifications.

### Waveform and noise section

Allows you to set the basis for the signal generated by the waveform generator. You can choose between four basic waveforms (sine, triangle, square, and sawtooth) and three types of noise (white, pink, and brownian).

### Frequency section

Allows you to set the frequency of the generated signal. You can set the frequency either in Hz or as a note value. If you enter a note value, the frequency is automatically changed to Hz. For example, a note value of A3 sets the frequency to 440 Hz. When you enter a note value, you can also enter a cent offset. For example, enter A5 -23 or C4 +49.

#### NOTE

Ensure that you enter a space between the note and the cent offset. Only in this case, the cent offsets are taken into account.

---

### Gain section

Allows you to set the amplitude of the signal. The higher the value, the stronger the signal. You can select one of the preset values, or use the slider to set a value between -81 and 0 dB.

## Tube Compressor

This versatile compressor with integrated tube-simulation allows you to achieve smooth and warm compression effects. The VU meter shows the amount of gain reduction. **Tube Compressor** features an internal side-chain section that lets you filter the trigger signal.



### VU Meter

Shows the amount of gain reduction.

### In/Out Meters

Show the highest peaks of all available input and output channels.

### Input

Determines the compression amount. The higher the input gain, the more compression is applied.

### Drive (1.0 to 6.0 dB)

Controls the amount of tube saturation.

### Output (-12 to 12 dB)

Sets the output gain.

### Character

Keeps the bass tight and preserves its attacks by decreasing the tube saturation for lower frequencies, and adds brilliance by creating harmonics for higher frequencies.

### Attack (0.1 to 100 ms)

Determines how fast the compressor responds. If the attack time is long, more of the initial part of the signal passes through unprocessed.

### Release (10 to 1000 ms or Auto mode)

Sets the time after which the gain returns to its original level. If **Auto Release** is activated, the plug-in automatically finds the best release setting for the audio material.

### Mix

Adjusts the mix between dry signal and wet signal, preserving the transients of the input signal.

### Ratio

Toggles between a low and a high ratio value.

### Side-Chain

Activates the internal side-chain filter. The input signal can then be shaped according to the filter parameters. Internal side-chaining is useful for tailoring how the gate operates.

## Side-chain section

### Filter Type (Low-Pass/Band-Pass/High-Pass)

If **Side-Chain** is activated, these buttons allow you to set the filter type to low-pass, band-pass, or high-pass.

### Center

If **Side-Chain** is activated, this sets the center frequency of the filter.

### Q-Factor

If **Side-Chain** is activated, this sets the resonance or width of the filter.

### Monitor

Allows you to monitor the filtered signal.

## VintageCompressor

**VintageCompressor** is modeled after vintage type compressors.

This compressor features separate controls for **Input** and **Output** gain, **Attack**, and **Release**. In addition, there is a **Punch** mode which preserves the attack phase of the signal and a program-dependent **Auto Release** function.



### VU Meter

Shows the amount of gain reduction.

### In/Out Meters

Show the highest peaks of all available input and output channels.

### Input

Determines the compression amount. The higher the input gain, the more compression is applied.

### Attack (0.1 to 100 ms)

Determines how fast the compressor responds. If the attack time is long, more of the initial part of the signal passes through unprocessed.

### Punch

If this is activated, the early attack phase of the signal is preserved, retaining the original punch in the audio material, even with short **Attack** settings.

### Release (10 to 1000 ms or Auto mode)

Sets the time after which the gain returns to its original level. If **Auto Release** is activated, the plug-in automatically finds the best release setting for the audio material.

### Mix

Adjusts the mix between dry signal and wet signal, preserving the transients of the input signal.

### Output (-48 to 24 dB)

Sets the output gain.

## VSTDynamics

**VSTDynamics** is an advanced dynamics processor. It combines three separate effects: **Gate**, **Compressor**, and **Limiter**, covering a variety of dynamic processing functions.



The window is divided into three sections containing controls and meters for each effect. Activate the individual effects using the **Gate**, **Compressor**, and **Limiter** buttons. You can select between three different routing options using the **Module Configurator** button.

### Gate

Gating, or noise gating, is a method of dynamic processing that silences audio signals below a set threshold. As soon as the signal level exceeds the threshold, the gate opens to let the signal through. The gate trigger input can also be filtered using an internal side-chain signal.

The following parameters are available:

#### **Input meter**

Shows the level of the input signal.

#### **Attack (0.1 to 100 ms)**

Determines how fast the compressor responds to signals above the set threshold. If the attack time is long, more of the early part of the signal passes through unprocessed.

#### **Threshold**

Determines the level at which the gate is activated. Signal levels above the set threshold trigger the gate to open, and signal levels below the set threshold close the gate.

#### **State LED**

Indicates whether the gate is open (LED lights up in green), closed (LED lights up in red), or in an intermediate state (LED lights up in yellow).

#### **Release (10 to 1000 ms or Auto mode)**

Sets the time after which the gate closes after the set **Hold** time. If **Auto Release** is activated, the plug-in automatically finds the best release setting for the audio material.

#### **Hold (0 to 2000 ms)**

Determines how long the gate remains open after the signal drops below the threshold level.

#### **Range**

Adjusts the attenuation of the gate when it is shut. If **Range** is set to minus infinite **-∞**, the gate is completely shut. The higher the value, the higher the level of the signal that passes through the shut gate.

#### **Side-Chain**

Activates the internal side-chain filter. The input signal can then be shaped according to the filter parameters. Internal side-chaining is useful for tailoring how the gate operates.

#### **Filter Type (Low-Pass/Band-Pass/High-Pass)**

If **Side-Chain** is activated, these buttons allow you to set the filter type to low-pass, band-pass, or high-pass.

#### **Center**

If **Side-Chain** is activated, this sets the center frequency of the filter.

#### **Q-Factor**

If **Side-Chain** is activated, this sets the resonance or width of the filter.

#### **Monitor**

Allows you to monitor the filtered signal.

### **Compressor**

**Compressor** reduces the dynamic range of the audio, making softer sounds louder or louder sounds softer, or both. It features a separate display that graphically illustrates the compressor curve shaped according to your settings.

#### **Input meter**

Shows the level of the input signal.

### **Graphical display**

Visualizes the settings for **Threshold** and **Ratio** and allows you to adjust them by dragging the handles.

### **Gain Reduction meter**

Shows the amount of gain reduction.

### **Threshold (-60 to 0 dB)**

Determines the level where the compressor kicks in. Only signal levels above the set threshold are processed.

### **Ratio**

Sets the amount of gain reduction applied to signals above the set threshold. A ratio of 3:1 means that for every 3 dB the input level increases, the output level increases by 1 dB.

### **Make-Up (0 to 24 dB or Auto mode)**

Compensates for output gain loss caused by compression. If **Auto Make-Up Gain** is activated, the output is automatically adjusted for gain loss.

### **Attack (0.1 to 100 ms)**

Determines how fast the compressor responds to signals above the set threshold. If the attack time is long, more of the early part of the signal (attack) passes through unprocessed.

### **Release (10 to 1000 ms or Auto mode)**

Sets the time after which the gain returns to its original level when the signal drops below the threshold. If **Auto Release** is activated, the plug-in automatically finds the best release setting for the audio material.

## **Limiter**

A limiter ensures that the output level never exceeds a set threshold to avoid clipping in effects following in the chain. Conventional limiters usually require a very accurate setup of the attack and release parameters to prevent the output level from going beyond the set threshold level.

**Limiter** adjusts and optimizes these parameters automatically according to the audio material.

### **Input meter**

Shows the level of the input signal.

### **Gain Reduction meter**

Shows the amount of gain reduction.

### **Soft Clip**

If this button is activated, the signal is limited when the signal level exceeds -6 dB. At the same time, harmonics are generated, adding a warm, tube-like characteristic to the audio material.

### **Output**

Sets the maximum output level.

### **Release (10 to 1000 ms or Auto mode)**

Sets the time after which the gain returns to its original level. If **Auto Release** is activated, the plug-in automatically finds the best release setting for the audio material.



## Output section

### Output meter

Shows the level of the output signal.

### Module Configurator

Changes the signal flow through the three effects. Changing the order of the effects can produce different results, and the available routing configurations allow you to quickly compare what works best for a given situation. Click **Module Configurator** to toggle between the following routing configurations:

- G-C-L (Gate-Compressor-Limiter)
- C-L-G (Compressor-Limiter-Gate)
- C-G-L (Compressor-Gate-Limiter)

# Legacy Plug-ins

Under Windows, a set of plug-ins is provided for compatibility with audio projects that referenced these effects when using earlier versions of WaveLab. An audio montage which referenced these plug-ins would otherwise require cumbersome user intervention to open, for example.


Their use with new audio projects is not recommended and they are not documented.

# Dithering Plug-ins

Dithering plug-ins add small quantities of noise to a signal to reduce the audibility of low level distortion in a digital recording. A small amount of random noise is added to the analog signal before the sampling stage, reducing the effect of quantization errors.

## Internal Dithering

This is a WaveLab-specific plug-in that provides a simple way of adding a small amount of noise to the rendered signal to improve the apparent signal-to-noise ratio of the output.



The following parameters are available when selecting **Internal Dithering**.

### Noise Type

Sets the noise type for adding to the signal.

- In **No Noise** mode, no dithering is applied.
- The **Noise Type 1** mode is the most all-round method.
- The **Noise Type 2** mode emphasizes higher frequencies more than **Noise Type 1**.

### Noise Shaping

Increases the apparent signal to noise ratio by altering the spectrum of the low-level audio signal which results from lowering the number of bits. The higher the number you select here, the more the noise is moved out of the ear's mid-range.

### Bit Resolution


Allows you to specify the intended bit resolution for the final audio, after dithering, regardless of whether you want to render the settings or play back in real-time.

Dithering changes the sample resolution, but not the sample size. For example, when dithering 24 bit to 16 bit, the file will still be 24 bit in size, although only 16 bits of information will have significance. When rendering to a 16-bit file, specify the file resolution to avoid wasting space.

## Lin Pro Dither

**Lin Pro Dither** is a dithering plug-in that uses advanced algorithms and offers additional noise shaping to increase the apparent signal-to-noise ratio by altering the spectrum of the low-level

audio signal. Different noise shaping types allow you to adapt the dithering effect to the audio material to be processed.



### Output Bit Depth

Sets the bit depth of the output signal.

#### NOTE

Dithering changes the bit depth, but not the sample size. For example, when dithering 24-bit to 16-bit, the file is still 24-bit in size, although only 16 bits of information have significance. When processing a 16-bit file, specify the **Output Bit Depth** value accordingly to avoid the creation of unnecessarily large files.

---

### Dither Control

If **Auto Blanking** is activated, the dither noise is gated during silent passages.

### Dither Type

Allows you to choose between **Triangular** and **Triangular Hi-Pass** dither types.

- If **None** is selected, no dithering is applied but the signal is still rendered to the set **Output Bit Depth**.

### Noise Shaping

Activates/Deactivates noise shaping. Noise shaping increases the apparent signal-to-noise ratio. The pop-up menu allows you to choose between different algorithms which move the noise to different frequency ranges.

#### NOTE

Noise shaping is not available if **None** is selected as **Dither Type**.

---

# Batch Processing Plug-ins

In the **Batch Processor** window, you can add a sequence of plug-ins that can be used to process a batch of audio files. These plug-ins can be standard plug-ins available from the **Master Section**, offline processes available in the **Audio Editor**, and plug-ins that are only available within batch processing.


The following batch processor plug-ins are described in the WaveLab Pro **Operation Manual**:

- **Loudness Normalizer**
- **Pitch Quantize**
- **Pitch Correction**
- **Pan Normalizer**
- **Time Stretch**

## Audio Analyzer

This plug-in allows you to generate text files with statistics about the audio files in a batch process.

This monopass plug-in is exclusive to the **Batch Processor** window.



If you want to analyze files without writing anything, select **No Output** in the **Output** tab of the **Batch Processor** window.

### Information to Report

In this section you specify which information to include in the output. The following information can be included:

- Sample rate

- Number of channels
- Real bit resolution
- Number of samples/duration
- Digital peaks
- True peaks
- Integrated loudness
- Loudness range
- Short-term loudness (maximum)
- Short-term loudness (minimum)
- Momentary loudness (maximum)
- Momentary loudness (minimum)
- Loudness balance
- DC Offset

## Output

In this section you set up the output of the **Audio Analyzer**. The following options are available:

### Send Analysis Results to XML Processor

If this option is activated, the analysis results are passed as parameters to the XML or HTML output of the batch processor.

### Create One Report per Audio File

If this option is activated, one report is created for each audio file in the batch process. The audio file name is used as the report file name.

### Merge Results into Global Report

If this option is activated, the results of the analysis are merged into a global report. The audio file name is used as the report file name.

### Open Global Report at End of Batch Process

If this option is activated, a global report opens after the batch process.

### File Name Suffix

Lets you specify a file name suffix. This is necessary when you are using this plug-in multiple times in a batch process, for example, to see the stats before and after specific plug-ins.

Use different suffixes for each instance of the **Audio Analyzer** plug-in used in the processing chain.


### Output format

Lets you select the output format. The following formats are available:

- Pure text
- HTML
- Adobe PDF
- Open Office
- Spreadsheet
- XML

## Audio Injector

This plug-in allows you to insert an audio file at the beginning and/or end of the audio file being processed. The inserted file can also be crossfaded with the original audio file, if required.



This monopass plug-in is exclusive to the **Batch Processor** window.

### Audio File to Inject at the Start (No Longer Than 60 Seconds)

Specifies the audio file to be added before the main audio file.

### Audio File to Inject at the End (No Longer Than 60 Seconds)

Specifies the audio file to be added after the main audio file.


### Perform Crossfade

Allows you to select a crossfade time and shape for the crossfade between the main audio file and the injected audio file.

## Audio Mixer

This plug-in allows you to mix an audio file with other audio files. The mix-in happens from a specified time and can optionally be repeated at a specified interval.

For example, you can insert a spectral watermark into the audio spectrum or you can insert beep sounds to mark an audio file as demo material.



This monopass plug-in is exclusive to the **Batch Processor** window.

### Audio File to Mix (No Longer Than 30 Seconds)

Allows you to select the audio file that you want to mix into other audio files. The audio file must be no longer than 30 seconds.

### Time Position

Allows you to specify the time position at which the audio file will be mixed in.

### Repeat Every

If this option is activated, you can specify the time after which the audio file is repeatedly mixed in.

## DC Remover


This plug-in allows you to remove any DC Offset from an audio file.

It is useful to apply this plug-in first in a batch before other plug-ins to avoid further processing a file containing any DC Offset. For example, an audio file that has a DC offset is not at its loudest possible volume when normalized, because the offset consumes headroom.

This multipass plug-in is available in the **Batch Processor** window and as an offline processor in the **Audio Editor**.

## Delay Next Process Activation

This plug-in allows you to delay the processing of the next VST plug-in in the plug-in chain for a certain time.



This monopass plug-in is exclusive to the **Batch Processor** window.

### Delay

Specifies the duration until the wet signal starts to fade-in the dry signal.


### Crossfade Time

Specifies the duration of the crossfade time.

## Fade In/Fade Out

This plug-in allows you to fade the beginning (**Fade In**) or the end (**Fade Out**) of a batch audio file. You can choose the length and shape of the fade, its duration, and the gain you want it to start/end at.

The fade plug-ins are exclusive to the **Batch Processor** window. **Fade In** is a monopass plug-in and **Fade Out** is a multipass plug-in.



### Shape

Determines the shape of the fade.

### Duration

Determines the duration of the fade.

### Start Gain/End Gain

Determines the gain with which the fade starts. It ends with 0 dB.



## Instructor

**Instructor** is a special utility plug-in that allows you to instruct the next plug-in in the batch with information about the audio it needs to process. This is useful for situations where you want to use monopass plug-ins that require an analysis stage that is not available at this point.

In effect, the **Instructor** plug-in turns a monopass plug-in into a dual pass one. Some monopass plug-ins, such as **DeNoiser** or **DeBuzzer**, need to learn about the audio they are to process before they can begin processing correctly. The **Instructor** plug-in can help in this situation, because it can teach the next plug-in in the audio chain about the audio it is about to process.

The **Instructor** plug-in must be used as a pair:

1. The first instance replicates the start of the audio stream. This means the next plug-in in the chain receives the start of the audio stream twice.
2. The second instance of the plug-in comes after the plug-in being instructed. It cuts out the extra audio injected by the first instance of the **Instructor** plug-in.

For example, this means that the **DeNoiser** plug-in has time to sufficiently analyze the audio stream before the second stream start is injected. The “badly” processed first part of the stream is skipped by the second instance of the **Instructor** plug-in.


You can set the **Instructor** plug-in to replicate up to 20 seconds of audio.

### NOTE

Do not set a value that is longer than the shortest file in the batch, otherwise a short file is over truncated by the second instance of the plug-in.

---

This monopass plug-in is exclusive to the **Batch Processor** window.



### Replicate Stream Start

Injects the start of the audio stream twice into the next plug-ins. This action must be selected for the first instance of the **Instructor** plug-in.

### Reverse Stream

If this option is activated, the start of the stream is injected first in reverse sample order, then in normal sample order. This changes nothing from the spectrum analysis point of view, but it improves the transition between the repeated streams.

### Trim Stream Start


Skips the start of the audio stream. This action must be selected for the second instance of the **Instructor** plug-in.

### Duration

Specifies how much audio to replicate or skip.

## Level Normalizer

This multipass plug-in allows you to raise or lower levels so that the signal peaks exactly at the specified value just before it is converted to a file.



### Peak Level

Specify the highest level of any audio sample.

### Stereo Link

Applies the gain to both channels.

### Mix to Mono

Mixes the left and right channels. The resulting mono file gets the specified peak level. This ensure a clip-less mix.

### Only if Clipping


Only applies a gain change if the audio file is beyond the reference peak level at some point. If not, the signal is untouched.

## Loudness Meta Normalizer

This plug-in allows you to normalize a batch of files to the same loudness, while taking the EBU R-128 loudness measurement and a true peak analysis into account.

The purpose of this plug-in is to achieve the same loudness in all files (the highest loudness found, if possible), while being certain that no file clips. For each file, a specific gain is computed by the plug-in once all files have been analyzed and prior to actually applying any gain to achieve the common loudness. If it is not possible to match the highest found loudness, the level of the file with the highest loudness is reduced, so that other files can get the same loudness. Because no peak compression is used, the dynamics is preserved and no distortion is introduced.

This metapass plug-in is exclusive to the **Batch Processor** window.



### Match Loudness

Select what loudness the clip should get. The following options are available:

- Match loudest audio file

- Match maximum achievable loudness
- Match specific loudness

### Loudness

Determines the specific loudness to match. For example, -23 LUFS if you want to follow the EBU R-128 recommendation for broadcast.

### Reference


Select whether WaveLab should use as reference the loudness of the entire clip (EBU R-128 recommendation), the average loudest 3 second audio section (**Top of Loudness Range**), or the loudest 3 seconds audio section (**Maximum Short-Term Loudness**).

### Peaks

Select whether WaveLab should refer to sample values (digital peaks) or to analog reconstructed values (true peaks).

## Loudness Restorer

**Loudness Restorer** captures the loudness at a specific point in the audio chain and restores that loudness at another point. For this reason, the **Loudness Restorer** must be inserted in pairs into the signal chain: one plug-in for capturing and one plug-in for restoring.



This multipass plug-in is exclusive to the **Batch Processor** window.

### Mode - Capture

The first instance in the plug-in pair must be set to this mode. This makes the plug-in read the signal at this position in the audio chain.

### Mode - Restore Peak Level/Restore Loudness (EBU R-128 Weighted)

The second instance in the plug-in pair must be set to one of these modes. Select one of these options if you want to use peak levels as a basis for determining what is considered equal level. **Restore Loudness (EBU R-128 Weighted)** produces a more natural result than **Restore Peak Level**.

### Reference menu

Select whether WaveLab should use as reference the loudness of the entire file (EBU R-128 recommendation), the average loudest 3 second audio section (**Top of Loudness Range**), or the loudest 3 seconds audio section (**Maximum Short-Term Loudness**).

### Peak menu

Select whether WaveLab should use sample values (**Digital Peaks**) or analog reconstructed values (**True Peaks**).


### Limit to 0 dB

If this option is activated, the restoration process will never result in levels above 0 dB.

## Meta Leveler

This plug-in allows you to change the level of a batch of files consistently.

The core purpose of this plug-in is to apply the same gain to all files, while being certain that a specific peak level never exceeds in any file. The unique gain that you want to apply is (possibly) reduced by the plug-in, once all files in the batch have been analyzed, and prior to actually applying the gain across the batch.



This metapass plug-in is exclusive to the **Batch Processor** window.

### Gain

Applies the specified gain to each file. The actual gain can be lower and even negative, to not exceed the value specified in the **Maximum Peak** field.

### Maximum Peak


Specifies the maximum peak level that any audio file should get at the end of the process.

### Peaks

Select whether WaveLab should refer to sample values (digital peaks) or to analog reconstructed values (true peaks).

## Resizer

This plug-in allows you to specify the duration of all audio files in the batch, and to choose whether to insert silence after the end of the chosen duration.




This monopass plug-in is exclusive to the **Batch Processor** window.

## Stereo to Mono

This plug-in allows you to mix a stereo signal down to a mono signal while being certain not to clip while mixing channels because of the multipass approach. You can choose to use the same

peak level that the stereo file contains, or set the gain to be applied and/or the maximum level to be reached in the resulting mono file.



This multipass plug-in is exclusive to the **Batch Processor** window.

#### **Keep Same Peak Level as Stereo File**

If this option is activated, the peak level of the resulting mono file is the same as the peak level of the original stereo file.

#### **Gain**


Specifies the increase or decrease in peak level for the resulting mono file, in relation to the original stereo file.

#### **Maximum Level of Mono Signal**

Specifies the peak level that the resulting mono file must not exceed. This ensure that the output file never clips. This way, the result never exceeds 0 dB, regardless of the specified **Gain** value.

## Trimmer

This plug-in allows you to remove a specified duration (from 0 ms to 60 s) of audio from the head and/or tail of an audio file.



This monopass plug-in is exclusive to the **Batch Processor** window.

# Index

## A

Amp Simulation  
  Quadrafuzz v2 69  
Analyzers  
  SuperVision 81  
Audio Analyzer 125  
Audio Injector 127  
Audio Mixer 127  
AutoPan 29

## B

Batch processing plug-ins 125  
  Audio Analyzer 125  
  Audio Injector 127  
  Audio Mixer 127  
  DC Remover 128  
  Delay Next Process Activation 128  
  Fade In/Fade Out 128  
  Instructor 129  
  Level Normalizer 130  
  Loudness Meta Normalizer 130  
  Loudness Restorer 131  
  Meta Leveler 132  
  Resizer 132  
  Stereo to Mono 132  
  Trimmer 133  
Brickwall Limiter 30

## C

Channel Extractor 31  
Chopper Effects  
  AutoPan 29  
Chorus Effects  
  Chorus 31  
  StudioChorus 112  
Compressor 32  
  MasterRig 12  
Compressors  
  Compressor 32  
  DeEsser 34  
  Maximizer 54  
  MultibandCompressor 58  
  Squasher 78  
  Tube Compressor 116  
  Vintage Compressor 117  
  VSTDynamics 118  
CurveEQ 33

## D

DC Remover 128

DeBuzzer 27  
  RestoreRig 23  
DeClicker 25  
  RestoreRig 23  
DeEsser 34  
Delay Next Process Activation 128  
Delays  
  MonoDelay 57  
  PingPongDelay 65  
  Quadrafuzz v2 69  
  StereoDelay 109  
DeNoiser 26  
  RestoreRig 23  
DeReverb 36  
Distortion 37  
Dithering  
  Lin Pro Dither 123  
Dithering plug-ins 123  
  Internal dithering 123  
DualFilter 38  
Dynamic EQ  
  MasterRig 18

## E

EBU R-128  
  Audio Analyzer 125  
  Loudness Meta Normalizer 130  
Envelope Shapers  
  EnvelopeShaper 38  
  MultibandEnvelopeShaper 61  
Equalizer  
  MasterRig 16  
Expanders  
  Expander 39  
  MultibandExpander 63

## F

Fade In/Fade Out 128  
Frequency 2 40

## G

Gates  
  Gate 47  
  Quadrafuzz v2 69  
  VSTDynamics 118

## I

Imager 50  
  MasterRig 21  
Instructor 129

Internal dithering [123](#)

## L

L/R to M/S [52](#)

Legacy plug-ins [122](#)

Level Normalizer [130](#)

Leveler [4](#)

Leveler Multi [5](#)

Limiter [52](#)

    MasterRig [9](#)

Limiters

    Brickwall Limiter [30](#)

    Limiter [52](#)

    Maximizer [54](#)

    VSTDynamics [118](#)

Lin Pro Dither [123](#)

Loudness Meta Normalizer [130](#)

Loudness Restorer [131](#)

## M

M/S to L/R [52](#)

Magneto II [53](#)

MasterRig [5](#)

    Compressor [12](#)

    Dynamic EQ [18](#)

    Equalizer [16](#)

    Imager [21](#)

    Layout [5](#)

    Limiter [9](#)

    Modules [8](#)

    Saturator [19](#)

    Settings [8](#)

Maximizer [54](#)

Meta Leveler [132](#)

Meters

    SuperVision [81](#)

Mix6to2 [55](#)

Mix8to2 [56](#)

MonoDelay [57](#)

MonoToStereo [57](#)

MultibandCompressor [58](#)

MultibandEnvelopeShaper [61](#)

MultibandExpander [63](#)

## O

Octaver [65](#)

## P

Peak Master [22](#)

PingPongDelay [65](#)

Plug-ins

    Batch processing [125](#)

    Dithering [123](#)

    Legacy [122](#)

    VST 3 [29](#)

    WaveLab-specific [4](#)

PostFilter [67](#)

## Q

Quadrafuzz v2 [69](#)

## R

Resampler [4](#)

Resizer [132](#)

Restoration

    DeReverb [36](#)

RestoreRig [23](#)

    Layout [23](#)

    Modules [25](#)

REvelation [72](#)

RoomWorks [74](#)

RoomWorks SE [77](#)

## S

Sample rate

    Resampler [4](#)

Saturation

    Magneto II [53](#)

    Quadrafuzz v2 [69](#)

Saturator

    MasterRig [19](#)

Silence [28](#)

Squasher [78](#)

Stereo Expander [28](#)

Stereo to Mono [132](#)

Stereo Tools [111](#)

StereoDelay [109](#)

StereoEnhancer [110](#)

StudioChorus [112](#)

StudioEQ [113](#)

SuperVision [81](#)

## T

TestGenerator [115](#)

Tools

    SuperVision [81](#)

    TestGenerator [115](#)

Trimmer [133](#)

Tube Compressor [116](#)

## V

Vintage Compressor [117](#)

VSTDynamics [118](#)